

Section 6. Working With Other Programs

6.1 Data Export via DDE Server.....	1
6.2 Exporting data using ODBC.....	6
6.3 Exporting instruments via ODBC.....	10
6.4 Points to be aware of when exporting data.....	11
6.5 Export of Data into Technical Analysis Systems Using Built-in Tools	11
6.6 Configuring Equis MetaStock	16
6.7 Configuring Wealth-Lab Developer.....	17
6.8 Configuring Omega TradeStation / ProSuite 2000	20
6.9 Configuring AmiBroker.....	23
6.10 Export of Data into Technical Analysis Systems using External Programs.....	26
6.11 Transaction Import.....	28
6.12 Importing transactions via API.....	42
6.13 APPENDICES	61

This section describes online interaction of the QUIK system with other programs, how to export information into other Windows applications (MS Excel, ODBC, Equis Metastock, Wealth-Lab Developer, Omega Tradestation / Prosuite 2000i), and how to import transactions from a file.

6.1 Data Export via DDE Server

menu Data export / DDE export... or button 

6.1.1 Purpose


DDE export allows the user to export data from QUIK tables into external programs, such as Microsoft Excel. Data is exported in the XLTABLE format using DDE method.

Please note that if any filters are applied to the tables, data from the tables in which you can insert or remove lines into the beginning or middle of the table (for example, cash and depo limits tables) will not be exported correctly via a DDE server.



6.1.2 Using data export

- Before configuring data export, a DDE server must be configured. To export data into MS Excel, open the program and load the file into which the data will be transferred (if the **Start DDE server automatically** option is disabled).



- To export data from an active table, use one of the following methods:

- click  on the toolbar;
- select **Data export / DDE export...**;
- hit **Ctrl+L**;
- select **Export via DDE server...** from the context menu.

- The **Export via DDE server...** configuration window contains the following options:

Option	Description
Table name	The QUIK table that serves as a data source
DDE server	The name of the DDE server. The Default button sets excel to this field
Workbook	The name of the file into which the information from the table will be exported. Click the '...' button on the right to select an existing file on your drive. If the excel is selected as a DDE server, the workbook file should have the .xls or .xlsx extension
Worksheet	The name of the worksheet into which information from the table will be transferred

Option	Description
Launch DDE server application automatically	Enable auto-opening of the selected workbook in MS Excel when export is started. This checkbox is enabled if excel is selected as a DDE server. The Workbook and Worksheet fields are optional
Upper left corner: – Row; – Column	The coordinates of the initial cell for data transfer: – The row number, counting from the top; – The column number, counting from the left
Export beginning from row	Export the table rows starting from the specified number. This option can be used to reduce the time of subsequent export of tables, for example, the Time and Sales table
Export after creation	Select this option to activate export immediately after the table configuration file is loaded, for example, after QUIK is started
Export by pressing Ctrl+Shift+L	When this checkbox is selected, you can start the export from a table by pressing this shortcut keys
With row headers	Output row headers of a QUIK table as the first column
With column headers	Output column headers of a QUIK table as the first row
Formal headers	Output the system (service) names of the headers. This feature can be useful for programming
Output blank cells instead of zeros	Output the cells that contain zeros as blank (not filled with numbers). This feature is useful for graphic display of data in MS Excel to prevent 'gaps' in chart lines where data is absent (not received from the server)

4. Click **Start export** to start exporting data from a table. If the **Launch DDE server application automatically** checkbox is selected, when this button is clicked, the program will attempt to launch MS Excel and load the specified workbook and worksheet. If MS Excel is not launched, the **Workbook** field must contain the name of the workbook with a full path to an existing file or must be empty.
- The names of workbooks in MS Excel that were created but not yet saved must be specified without extension, for example, Workook1. If the workbook name is specified without extension, the program will try to find this book among those already open in MS Excel, and, if the book is not found, create a new book. The name of that new book might be different from the name specified in the **Workbook** field.
- If no book name is specified, MS Excel will create a new book when launched. If no worksheet name is specified, the program first searches for the worksheet with the name of the table being exported (for example 'Order table #2') and if it is not found, a new worksheet with this name will be added. If other tables are exported into MS Excel and the workbook name is not specified, the same workbook will be used.



If a file name without full path is specified in the **Workbook** field, the program will search for that file in the current work directory. The system displays an error message if the file is not found.

5. You can stop export of data from a table by clicking **Stop export**.
 6. The **Export now** button is intended for one-time data export.
 7. Click **Close** to save configured settings and close the export configuration window. If the export process is started, it will be performed automatically in the background.
 8. Click **Cancel** to close the window without saving the settings.
 9. Click **Help** to open the help window for this feature.
-
1. When any settings window is opened in MS Excel, the data is stored in the DDE buffer instead of being transferred to Excel tables. If Excel is busy for a long period, data transfer might be interrupted. DDE connection timeout (if MS Excel is busy) can be specified in the export configuration.
 2. Each table has its own data export settings; therefore, different tables can export data to different DDE servers, files, MS Excel worksheets or cells.
 3. Data from a QUIK table can be exported only to one DDE server.
 4. However, one DDE server can accept exported data from several QUIK tables. For example, you can export data from different QUIK tables into different cells of a single MS Excel worksheet.
 5. If table format is changed, the system stops export and opens the export configuration window so that the user can set new parameters for data export.
 6. Using filters in tables to be exported is not recommended when exporting via DDE. If the configuration of a table has the Show zero values option, enabling this option is recommended.
 7. DDE export of tables is performed according to the default sorting settings; current sorting settings are ignored.

6.1.3 DDE export settings

menu **Settings / General...**, section **Program / Data export**

Settings 1-3 are used to configure the handling of timeouts if the DDE server is busy.

1. Time during which data receipt confirmation is pending:
 - If the whole table is exported (1-3600) sets a timeout for initial data transfer. The recommended value is 20;
 - If the next row is exported (1-600) sets a timeout for updating data. The recommended value is 5.
2. Number of attempts to resume if export fails sets the number of permitted attempts to restore the connection when a transmission fails. The default value is 0.
3. New thread for each DDE server enables multithread data export to different DDE servers. The default setting is OFF.



- 4.** Microsoft Excel supports localised versions of Microsoft Excel for different languages. The default language is English. If a Russian version of Microsoft Excel is available, this feature allows the use of English or Russian.

To avoid interruptions during data transfer when the DDE server is busy (e.g., when configuring formulas in a Microsoft Excel spreadsheet), the second parameter may be increased to 30-40 seconds.

6.1.4 Useful hints

- 1.** For simple data export to a DDE server you can copy a QUIK table by selecting **Copy table** from the context menu or by pressing **Ctrl+C**. Then, you can just paste data into MS Excel (the **Edit / Paste** menu or **Ctrl+V**).
- 2.** If the DDE server needs to be configured before processing exported data, use the **Export now** function first. The data will be exported once and become available for you to configure the settings. In this case DDE buffer will not be overflowed and the export will not be terminated. After configuration is complete, you can enable dynamic data export by clicking the **Start export** button.
- 3.** If simultaneous export of data to a DDE server from several tables was interrupted and it is difficult to resume it manually, you can load a saved configuration of tables with export settings from a file (the **Export after creation** checkbox must be selected). Export will resume automatically.
- 4.** QUIK lets you create any number of tables of the same type. To facilitate export of data, you can create a separate tab, e.g., ‘For export’, and put all data source tables into it. Thus, (1) those tables will not take space on the screen space, (2) it will be easier to find which tables are used for export, (3) if a DDE connection is terminated, it will be easier to find the tables for which export was suspended.
- 5.** When exporting from several tables, it is recommended that the **Export by pressing Ctrl+Shift+L** checkbox be checked. This enables manual start of export by simply pressing this keyboard shortcut.
- 6.** Export of multiple tables can be stopped by using the **Data export / Stop DDE export from tables** command or ‘**Ctrl+Shift+S**’ keys.

6.1.5 Error Messages

- 1.** ‘Failed to establish DDE connection. Excel is not running or the [Workbook][Worksheet] worksheet is not loaded.’
 - The DDE server or MS Excel is not running. Open the program and load the required file into it;
 - Incorrect name of an MS Excel Workbook (file) or its worksheet. The file name in the **Workbook** field must exactly match the name in MS Excel. If the file has been saved earlier, it has an extension and must be specified with that extension, for example, **quikexp.xls**. The names of MS Excel workbooks that haven’t been saved as files have no

extensions (for example, Workbook1) and should be specified without extensions in the export settings;

If the setting **Start DDE server automatically** is not selected then you should specify only name of the file in **Workbook** field, do not specify the path to this file;

- The **Ignore DDE request from other applications** checkbox is selected in the MS Excel settings (the **General** tab under **Service / Parameters**). Clear it.

2. ‘Data exchange timeout: server overloaded.’

- DDE connection is lost due to overload of the DDE server (MS Excel). If the server was busy because some configuration windows were opened for a long time, close those windows and start dynamic export from the **DDE export** window again. If disconnections occur regularly, increase the timeout for outputting a line (the **Program / Data export** section under **Settings / General...**), for example, to 30-40 seconds.

3. ‘Failed to launch Excel’

- The MS Excel program is not found on the computer.

4. ‘Failed to open [Workbook] workbook in Excel, [Exported table] table’

- The file with the specified name does not exist in the specified path or (if no path is specified) it is not found in the current working folder.

5. ‘The [Worksheet] worksheet is not found in the [Exported table] table of the [Workbook] workbook’

- The specified workbook does not contain a worksheet with the specified name.

6.2 Exporting data using ODBC

menu **Data export / ODBC export...** or 

6.2.1 Purpose

ODBC export allows the user to export data from QUIK tables to other applications for further use (storage, processing). This function can be used to directly connect the QUIK system with other programs that require online information from an exchange.




The screenshot shows the Microsoft Access 'Field Properties' dialog box. At the top, there is a table titled 'Time_and_Sales' with columns 'Field Name', 'Data Type', and 'Description'. Below this is a list of fields: Number, Date, Time, Security_(s.n.), Security, Security_code, Class, Price, Quantity, Volume, Operation, Settlement code, Yield, ACI, REPO_rate, REPO_sum, REPO_buyback_volume, and REPO_term. The 'Number' field is selected. In the 'Field Properties' dialog, the 'General' tab is selected. The 'Field Size' is set to 'Long'. The 'Format' dropdown is set to 'Auto'. The 'Caption' is empty. The 'Default Value' is '0'. The 'Validation Rule' is empty. The 'Validation Text' is empty. The 'Required' checkbox is checked. The 'Indexed' checkbox is checked. The 'Smart Tags' dropdown is set to 'No'. The 'Text Align' is set to 'General'. A note in the dialog states: 'An index speeds up searches and sorting on the field, but may slow updates. Selecting "Yes - No Duplicates" prohibits duplicate values in the field. Press F1 for help on indexed fields.'

Time_and_Sales		
Field Name	Data Type	Description
Number	Number	
Date	Text	
Time	Text	
Security_(s.n.)	Text	
Security	Text	
Security_code	Text	
Class	Text	
Price	Text	
Quantity	Text	
Volume	Text	
Operation	Text	
Settlement code	Text	
Yield	Text	
ACI	Text	
REPO_rate	Text	
REPO_sum	Text	
REPO_buyback_volume	Text	
REPO_term	Text	

6.2.2 Using ODBC data export

- Before exporting data, the user should create a table that will receive this data. The structure of this table should be similar to the structure of the QUIK table from which data will be exported. In other words, its list of parameters should be the same as the list of column headers of that QUIK table. The list of table parameters and their data types are provided in the appendix to this section. As an example, let us consider export of a trade table into a Microsoft Access table (see fig.).
- After a table is created, it should be registered as an ODBC data source in the Windows Control Panel (select **ODBC data sources** in the **Start / Settings / Control Panel** menu).
- In the QUIK system, you can activate the table from which data will be exported and open the ODBC export configuration window using one of the following methods:
 - Click on the toolbar;
 - Select **ODBC export** from the shortcut menu;
 - Select **Data export / ODBC export...** or press **Ctrl+O**.
- Select a data recipient in the **Choose ODBC data source name** list. The name should be the same as described in item 2.

- If user authorization is required for connection to the source, enter the user name and password into the corresponding field.
- Click **Connect**. The full list of tables from the selected source will appear in the **Available tables** list.



- Select the table to which data will be exported. The fields of the selected table will be displayed in the **Table fields list**.
 - Configure the correspondence between the fields of the QUIK table and that of the recipient table by performing the following actions for each field:
 - Select a field of the QUIK table from the **Parameters list**;
 - Link it with a field from the **Fields that correspond to the parameter** list. This list displays fields that are compatible with the type of the field of the QUIK table. If there is no required field, see sub-section [6.2.4 Error Messages](#).

It is not necessary to link all fields of the tables. You can do it only for the fields that contain parameters to be exported. However, the fields marked with '*' must be linked with their counterparts.
 - If you want to remove the link between the fields, select the field of the QUIK table in the **Parameter list** and click **Clear**. If you want to apply this to all fields, click the **Clear all** button.
- If a recipient table was selected erroneously, when you select another table from the List of available tables, the links between the fields that have the same names**

and data types will remain. This won't apply to fields with different names or data types.

10.Purpose of export settings:

- **Clear table before export** removes old data from the table before export or when the session, sever or user is changed; if this checkbox is cleared, new data will replace the old data as it is received;
- If **Use formal names** is selected, the system identifiers of the parameters will be exported instead of their text values. For example, instead of an instrument's name and class, their codes in a trading system will be exported; enumerable types, such as 'order direction', will be replaced with the symbol codes (for example, 'B' for buying 'S' for selling);
- If the **Export after creation** checkbox is selected, data export will begin simultaneously with loading the window configuration into the QUIK system, for example, when the program is launched;
- When the **Export by Ctrl+Shift+O** checkbox is selected, you can activate export from a table by pressing this keyboard shortcut.

11.Click the Start data export button to start export.

When exporting data from the Quotes Table, make sure that the Current and historical data option is selected in the data reception configuration (the Settings / General... menu, then the Program / Saving data section).

12.Click Stop data export to stop data export.

13.Click OK to close the export configuration window saving the changes. If the export process is started, it will be performed automatically in the background.

14.To close the export configuration window without saving any changes, click Cancel.

6.2.3 Useful hints

1. Do not use reserved words such as 'money', 'group', 'order', 'number', 'date', etc, to name table fields.
2. Do not use spaces in table names, table fields, and paths to tables.
3. To export data from QUIK tables that contain parameters with the '*' symbol, enable the **Clear table before export** checkbox. This will remove all data related to previous server connection sessions.
4. If you need to archive information received from QUIK in a database, we recommend creating two tables with the same structure. Use one of them to store data from QUIK and the other as an archive. Copy data to the archive at the end of a trading session or at the beginning of the next one. You can thus avoid saving the data twice, for example, in case when you need to load data from the QUIK system again.



5. Data from one QUIK table can be exported only to one recipient table. However, you can configure several identical tables in QUIK to be exported into different applications.
6. If data export is used regularly, check the **Export after creation** box in the export settings. When it is enabled, the export procedure will start automatically when the program is launched.
7. If several tables are used for data export, for convenience, we recommend creating a separate tab and putting the tables in it. This would keep data export configuration from possible changes in a similar table used to view market information.
8. When exporting from several tables, it is recommended that the **Export by pressing Ctrl+Shift+O** checkbox be selected. This enables manual start of export by simply pressing this keyboard shortcut.
9. If the tables in the database are indexed using a key, to ensure uniqueness, this field should be configured to correspond to the **Order number** and **Class code** fields in QUIK.
10. If the configuration of a table has the **Show zero values** option, enabling this option is recommended.

6.2.4 Error Messages

1. ‘Syntax error during INSERT INTO operation.’
The most common error caused by ignoring hints 1 and 2.
2. ‘Connection error. Not enough information to connect to DSN.’
The ODBC data source is not configured or incorrectly configured. See sub-section [6.2.2](#), item 2.
3. ‘The data recipient is not specified in the data source list.’
 - The table is not registered in the list of ODBC data sources. See sub-section [6.2.2](#), item 2;
 - A field from the **Table field list** does not have a corresponding field in the **Fields that correspond to the parameter** list;
 - A field in the recipient table is incompatible with the type of the QUIK table field. The field type in the recipient table must match its corresponding field in the QUIK table.

6.3 Exporting instruments via ODBC

menu **Data export / ODBC export instruments...**


6.3.1 Purpose

Exporting orders queues for instruments (DOM) through ODBC without creating Level II Quotes tables for them.

6.3.2 Using instruments export

1. Configure a list of instruments to be exported by generating the **Selected instruments** list from available instruments.
2. Click the **Configure** button to configure the list of parameters to be exported. Parameters are configured as described in sub-section [6.2.2](#).
3. To begin export, click **Start**. To stop export, click **Stop**.





Click **Yes** to close the export window and save all parameters. Click **Cancel** to close the window without saving the configured settings.

Sparse Level II quotes are exported using DDE in the non-sparse form.

6.4 Points to be aware of when exporting data

There are several points that you should be aware of when exporting data via DDE or ODBC from the tables operating in the ‘drag-and-drop’ mode:

1. When columns are moved or deleted in the ‘drag-and-drop’ mode (**Tables / Ask for confirmation when moving and deleting items using Drag-and-Drop** under the **Settings / General** menu) from the tables for which DDE / ODBC export is configured, the system will reload export settings and display the configuration window.
2. If user filters are applied to a table (menu **Settings / General...**, section **Tables / Use table filters**), when the filters change, the system will reload DDE/ODBC export configuration and display the appropriate configuration window.
3. The user can delete or change the order of rows using ‘drag-and-drop’ in the Quotes table, the **Option parameters table** and the **Buy / Sell** table. The **Options board** table allows you only to remove rows in this mode. When these actions are performed, the system reloads export settings and opens the appropriate configuration dialogue.

6.5 Export of Data into Technical Analysis Systems Using Built-in Tools

menu **Data export / Data for technical analysis system...**

6.5.1 Purpose

This feature allows the user to use the data obtained by the QUIK system for dynamic technical analysis in business applications, such as Equis MetaStock (including version 9.0), Wealth-Lab Developer versions 3.0 and 4.0, Omega TradeStation / ProSuite 2000i and AmiBroker 5.x.




6.5.2 Using data export

You can export data using the built-in tools if the **Data export / Data for technical analysis system...** menu is available.


To ensure proper operation of technical analysis packages, they must be properly configured; for further details, see sub-sections [6.4-6.8](#).

The built-in export tools and MetaServer RT cannot be used simultaneously to export data into MetaStock or TradeStation since they both use the same data transfer mechanism. Also note that installing other internet trading systems that can export data to technical analysis programs can block export from the QUIK system.

1. To open the export configuration window, select **Data export / Data for technical analysis system....**



2. Create a list of instruments and their parameters to be exported. To add an instrument to that list, click **Add**. The export parameters selection dialogue will open.




3. Select the desired instrument from the list of available securities. By default the list is sorted in alphabetical order. To make selection of instruments with limited period of circulation easier, check the **Sort by expiry date** checkbox.
4. In the **DestinationTA system** field, select the program into which the data will be exported.
5. In the **Security TA ticker** field, enter the same instrument name that you specified in the data source settings for the technical analysis system.
6. Select a data source for export. From the **All trades table (price and volume)** you can export prices and volumes for each trade. If the **Export trade volume in lots** is enabled, the volume of instruments in the last trade will correspond to the number of lots in the trade; when this checkbox is cleared, the volume will correspond to the number of instruments. From the **Quotes History** table you can export a larger number of parameters, such as **Best bid price** and **Best offer price**.
7. The **Interval** parameter determines the intervals at which the 'candlesticks' are drawn on a chart. If you select the **Tick** value, data will be exported for each trade. You cannot select the **Daily** interval to export data into Omega TradeStation or Metastock.
8. The **Export data...** and **to...** parameters determine the beginning and end of a trading session. Edit those parameters to exclude trades in opening and closing periods when the prices might be significantly different from market averages.
9. If the **Ignore already exported data** checkbox is checked, if the server connection is lost and then restored, QUIK will not transfer data that has been already transferred. If this box is clear, whenever the server connection is restored, QUIK will export all data from the beginning of the current trading session. See use cases in sub-section [6.2.3 Useful hints](#).
10. The following parameters determine the amount of exported data:
 - Select **All available values** to export all values including historical data for previous days if the broker's QUIK server supports this function;


- Select **Export intraday data only** to export all values in the current trading session;
- Fill in the **From...** and **to...** fields to export values from the specified period.

The parameters no. 7-10 by default are configured according to general data export settings (the **Common settings button in the configuration dialogue for exporting data to technical analysis systems).**

11. Click **Yes** to close the instrument parameter selection window. The new instrument will be displayed in the **Exported securities** list.
12. To edit an instrument created earlier, click the **Edit** button.
13. To edit the common export parameters for several instruments, highlight the desired instruments in the list and click **Edit**. The dialogue window will open that allows you to change export settings such as export period, repeated export of data, and the range of exported values.



14. To remove instruments from this list, highlight them and click **Remove**.
15. The **Common settings** button allows the user to specify default parameters that would be used when a new instrument is added for export. This button opens the following dialogue window:



- The **Interval** parameter determines the intervals at which the ‘candlesticks’ are drawn on charts for all exported instruments;
- The **Export data...** and **to...** parameters determine the beginning and end of a trading session;
- If the **Ignore already exported data** checkbox is checked, if the server connection is lost and then restored, QUIK will not transfer data that has been already transferred. If this

box is clear, whenever the server connection is restored, QUIK will export all data from the beginning of the current trading session;

- The following parameters determine the volume of exported data (apply to all instruments in the list):
 - Select **All available data** to export all values including historical data for previous days if the broker's QUIK server supports this function;
 - Select **Intraday only** to export all values in the current trading session;
 - Fill in the **From... to...** fields to export only the parameters for the specified interval. For example, if you do not want to export data on trades executed during the first minute of a trading session, you can configure transfer of data not from the very beginning of trading, but from the specified time.

16.If **Start export automatically** is checked, data export will begin as soon as the program launches.

17.Click the **Start export for security** button to start export procedure for a selected instrument. The instruments that are being exported are marked with the ➤ symbol in the list.

18.Click **Start export** to start export procedure for all instruments in the list.

19.The **Stop export for security** button stops export for a selected instrument, while **Stop export** stops export procedure for all instruments in the list.

After export of data for an instrument starts, that instrument cannot be removed from the list and its settings cannot be changed. If you need to make any changes, first stop data transfer, then edit the list of instruments to be exported.

20.Click the **Close** button to close the export configuration window. If the export process is started, it will be performed automatically in the background.

6.5.3 Useful hints

1. Check the **Ignore already exported data** box in the QUIK export configuration. If the server connection was lost and then restored, data export will be resumed automatically. Only newly received data will be transferred.
2. If the QUIK program is closed by the user, data export stops. When the system is launched again, data is exported from the beginning of the current trading session. In this case, you will have to clear data for the current day in Metastock and start data transfer again, following these steps:
 3. Open The DownLoader program included in the MetaStock package.
 4. Clear data on the securities that were exported during the current trading session. Go to the **Tools / Delete / Data...** menu, select each security one by one and deleted them by clicking **Delete**.
 5. Enter the date for the current trading session and click **OK**.
 6. Equis DataServer and Metastock FileServer must be restarted after that. If DataServer is not restarted, all previous data will be displayed in a single time interval ('candlestick').




- Start data export from QUIK by clicking the **Start export** button.

6.5.4 Error Messages


- After reconnecting to the server, data for the missed period does not appear in MetaStock.
Most Likely the Replace vendor-supplied times with computer system time option is enabled in the MetaStock's settings (Start / Programs / Equis / Equis Real Time Configuration). Disable it.

6.6 Configuring Equis MetaStock

- When installing version 7.0 or later of this program, you need to specify the **Signal (Broadcast version)** in the **Select Real-Time Vendor** dialogue window.
- Before first launch of MetaStock:
 - Make sure that files WinRos.exe and iwr.dll are present in the QUIK installation directory;
 - Launch QUIK.



- Open The Downloader program included in the MetaStock package.
- Create a new data source by selecting **File / New / Security** in the menu.



- Enter a name for that data source in the **Name** field, for example, 'Sberbank'.
- Enter an instrument designation in the **Symbol** field, for example, 'SBER'. This designation must be the same as the instrument's designation in QUIK export settings.
- Enter the current date in the **FirstDate** field (this is the default value).
- Select **Intraday** in the **Periodicity** field. The **Interval**, **Start Time** and **End Time** fields will become available.

9. Select **Decimal** in the **Units** field.

10. In the **Interval** field enter the time interval at which new data will be received. **1 Minute** is recommended.

This parameter is set once and cannot be changed in the future.

11. In the **Start Time** and **End Time** fields enter the beginning and end time of a trading session.

12. Click **Create** to proceed to the next instrument's configuration. Click **OK** to finish configuration.

If you need to re-export data for the current trading session, follow the recommendations given in sub-section [6.5.3](#).


6.7 Configuring Wealth-Lab Developer

6.7.1 Getting started

1. Install the Wealth-Lab Developer program.
2. Download the installation package for the program that performs export from QUIK into Wealth-Lab Developer. It can be downloaded from: <http://www.quik.ru/depot/quik2wld.exe>.

6.7.2 Configuring a data source in QUIK

1. Open the export configuration window in QUIK (select **Data export / Data for technical analysis...**).
2. Create a list of instruments and their parameters to be exported. To add a security to that list, click **Add**. The export parameters selection dialogue will open.



3. Select the desired instrument from the list of available securities, for example, 'Sberbank'. By default the list is sorted in alphabetical order. To sort securities with limited period of circulation, use the **Sort by expiry date** option.

4. Select **WealthLab** in the **TA system** field.
5. Enter an instrument identifier in Wealth-Lab Developer into the **Instrument identifier in TA system** field.
6. Select a data source for export. From the **Anonymous (all) trades** table you can export prices and volumes for each trade. If the **Export trade volumes in lots** is enabled, the volume of instruments in the last trade will correspond to the number of lots in the trade; when this checkbox is cleared, the volume will correspond to the number of instruments. From the **Quotes History** table you can export a larger number of parameters, such as **Best bid price** and **Best offer price**.
7. In the **Interval** field select an interval at which data will be exported into Wealth-Lab Developer.
8. Select the beginning and the end time of a trading session.
9. If the **Do not export data again** checkbox is checked, if the server connection is lost and then restored, QUIK will not transfer data that has been already transferred. If this box is clear, whenever the server connection is restored, QUIK will export all data from the beginning of the current trading session.
10. Set parameters that determine the volume of exported data (for the selected instrument).
11. Click **Yes** to close the instrument parameter selection window. The new instrument will be displayed in the **Exported securities** list.

6.7.3 Configuring data import in Wealth-Lab Developer

1. Launch Wealth-Lab Developer and select **DataSources / Enable Live Feed / QUIK Real-Time Data Adapter** from the menu. If import is started successfully, the program's status bar will display the 'QUIK RTAdapter' message.
2. To create a chart, select **File / New ChartScript** or click the corresponding button on the toolbar.
3. In the window that opens, in the **Symbol** field enter the same ticker name that you specified in the configuring the data source in QUIK. In this case you should enter 'SBER' and press Enter.



4. After that the SBER ticker will appear in the **QUIK Real-Time Data Adapter** folder. Select it.




5. Since in this example data will be exported in ticks, select display in ticks for the SBER ticker as shown in Fig.




6. Chart display type can be selected under the **Chart** menu (columns, candlesticks, lines). Select **lines (Chart / Line)** to create a tick chart.
7. Then, launch export from QUIK by clicking the **Start export** button in the **Export data for technical analysis** window.
8. To create the chart, click **Go** on the **ChartScript** form next to the **Symbol** field in Wealth-Lab Developer.



A chart similar to the one on the figure will be displayed.



9. The number of ticks displayed on a single chart segment can be configured from the **Chart** menu or by clicking the buttons on the toolbar. To display every trade as a separate chart segment, select **1 Tick Bars**.




6.8 Configuring Omega TradeStation / ProSuite 2000


To use data export in the online mode, this program must be installed appropriately. If the program is already installed, we recommend you to reinstall it following the instructions below.

6.8.1 Notes for program installation


1. In the 3rd Party Data Vendor Software dialogue, select the DBC – Supports: Signal Broadcast, eSignal Online, and InSite Online option.
2. In the next dialogue DBC Data Feed Selection, select the eSignal Online option.
3. After the program is installed and the computer restarts, installation of the DBC eSignal program will be launched automatically. Cancel the installation of this program.
4. Install the DBC Signal program. Usually it is located in the Omega ProSuite installation package, in the DBCSetup folder.
5. Restart your computer after the installation.



6. When Omega Research ProSuite is first launched, it will ask the user to configure Global Server. Select the **Launch the GlobalServer Setup Wizard** option.
7. Then, in the **GlobalServer Setup Wizard – Data Collection Method** dialogue window, select the **Real-Time / Delayed...** option.




8. In the GlobalServer Setup Wizard – Select Datafeed dialogue window, select the DBC Online SubServer option.
9. In the GlobalServer Setup Wizard – HISTORYBANK.COM dialogue window select No.



- 10.** When Global Server is first launched, select the Start Online mode in the operation mode selection dialogue window.


6.8.2 Configuring data flow received in GlobalServer

1. Launch QUIK before opening Omega Research ProSuite and Global Server.
2. Open GlobalServer and create a new data source by selecting **Insert / Symbol** from the menu and clicking **Add New**.
3. In the dialogue window that opens, fill in the following fields:




- In the **Data Source** field, select **DBC Online**;
- Select **Stock** in the **Category** field;
- Enter the name for the data source being created in the **Symbol** field, for example, '**SBER**';
- Select **Autodetect** in the **Exchange** field;
- Click **OK** to proceed to the **Add stock** data source configuration dialogue.






4. On the **Stock** tab, enter the value ('SBER') that you entered in the **Symbol** field of the previous window into the **Trading Name**, **Description** and **Symbol Root** fields.
5. On the **Sessions** tab, fill in a Trading session's schedule, following the example provided below:



6. In the Display Session Times in: field, select Local Time.
7. Click OK after you have finished configuration, and answer OK to all of the questions that will follow. The data source will be created and will be displayed as a new row in System portfolio.



8. Right-click the new source row and select **Connect symbol** from the context menu. If data transfer from QUIK is established, the **Real-Time status** parameter will change to **Connected**. If this did not happen, then something was done incorrectly during the previous steps.
9. After configuring data sources in GlobalServer, you can start configuring the data export in QUIK (see sub-section [6.5.2 Using data export](#)).

6.8.3 Additional information for this section

Guidelines for configuring time in Omega Tradestation / ProSuite2000:

<http://www.howtotrade.ru/forum3/posts/154.html>


6.9 Configuring AmiBroker

6.9.1 Getting started

1. Install AmiBroker.
2. To set up export from QUIK into AmiBroker you'll need QUIK2AMIBROKER_DataPlugin.dll. It can be downloaded from [the official website of QUIK](#).
3. Copy the QUIK2AMIBROKER_DataPlugin.dll file into the **Plugins** folder in the AmiBroker directory.

6.9.2 Configuring a data source in QUIK


1. Open the export configuration window in QUIK (select **Data export / Data for technical analysis...**).
2. Create a list of instruments and their parameters to be exported. To add a security to that list, click **Add**. The export parameters selection dialogue will open.



3. Select the desired instrument from the list of available securities, for example, 'Lukoil'. By default the list is sorted in alphabetical order. To sort securities with limited period of circulation, use the **Sort by expiry date** option.
4. Select **AmiBroker** in the **TA system** field.
5. Enter an instrument identifier in AmiBroker into the **Instrument identifier in TA system** field.
6. Select a data source for export (**Anonymous (all) trades** table or **Quotes history** table).
7. In the **Interval** field, select an interval at which data will be exported into AmiBroker.
8. Select the beginning and the end time of a trading session.
9. If the **Do not export data again** checkbox is checked, if the server connection is lost and then restored, QUIK will not transfer data that has been already transferred. If this checkbox is clear, whenever the server connection is restored, QUIK will export all data from the beginning of the current trading session.
10. Set parameters that determine the volume of exported data (for the selected instrument).
11. Click **OK** to close the instrument parameter selection window. The new instrument will be displayed in the **Exported securities** list.

6.9.3 Configuring data import in AmiBroker

1. Launch AmiBroker and select **Database...** under **File / New**.
2. In the **Database folder** field in the window that opens, specify the path to the database in which the imported information will be stored. If there is no database, you need to create it. To do this, specify the path and unique name and click **Create**. Select **Load this database at startup** to load the specified database upon program launch.




3. Then configure data import settings. Select **QUIK Data Plug-in** as a data source in the **Data source** field.
4. The **Local Data Storage** parameter must be set to **Enable** (the default setting).
5. Specify the number of bars to be displayed in a chart in the **Number of bars** field.
6. Specify the data import interval in the **Base time interval** field.

- The value of the Base time interval parameter must be the same as the value of the Interval field in QUIK export settings for AmiBroker (see sub-section [6.9.2](#)), otherwise data can't be exported.**
- AmiBroker allows the user to change chart intervals through the context menu (select Intraday in the menu) based on the global chart settings in the Database settings. After changing a chart's timeframe configuration, the chart in Amibroker is usually different from the chart exported from QUIK due to specific way of generating chart intervals in the QUIK system. QUIK divides an hour into intervals specific for the chart (for example, into 15-minute intervals) and displays the first chart bar in the next closest interval. AmiBroker plots charts in a different way, so the charts may differ.**

- Click **OK** to save your settings.
- After the settings are saved, the **Configure** button will become available. Press this button to open the **Settings for data export from Quik to AmiBroker** window. Set the **Clear AmiBroker data after establishing connection** flag to remove all data transferred to AmiBroker before starting a new export session from QUIK. If this flag is not set, new data will be added to the previous data, i.e., AmiBroker will store quotation history.
- Then you should create a new ticker. Select **New** under the **Symbol** menu. In the window that opens, enter the same ticker name that you specified when configuring the data source in the QUIK system (see sub-section [6.9.2](#)). In this example, enter 'LKOH' and press Enter.



- In the **Symbols** window you can see the list of all created tickers. When you select a ticker, the chart that corresponds to that ticker will be displayed in the AmiBroker's workspace.



- To start export, click the **Start export for security** button in the **Export data for technical analysis** window in QUIK. The received data will be displayed in real time in the AmiBroker's workspace during the process.



6.10 Export of Data into Technical Analysis Systems using External Programs

6.10.1 Purpose

This function allows the user to perform dynamic technical analysis of the data gathered by QUIK using Equis MetaStock in case the built-in export tools are unavailable.

6.10.2 Usage

There are two common ways to export information: using the DDE2MS or MetaServer RT. Both programs transfer information as follows:

- Data is transferred from QUIK's **Quotes Table** into Microsoft Excel via DDE;
- DDE2MS or MetaServer RT obtains continuously updated data from Microsoft Excel and transfers it to MetaStock.

QUIK → Microsoft Excel → DDE2MS or MetaServerRT → MetaStock

In our opinion, DDE2MS is more convenient to configure and work with, but, unlike MetaServer RT, whose demo version can download data for two securities, DDE2MS can only work with one. You can choose either of these options.



6.10.3 Using DDE2MS

1. Launch the DDE2MS program (it comes as a portable .exe file that does not need installation).
2. Specify parameters required for operation:
 - In the **Path** field, specify the full path to the MetaStock data source you created (for example, C:\MetaStock Data\SBER);
 - In the **Symbol** field specify the data source name ('SBER' in this example);
 - Select '1' in the **Interval** field;
 - Enter 'Excel' in the **Server** field;
 - In the **Topic** field, specify which Worksheet and Workbook data will be taken from: in the format '[book_name.xls]sheet_name', for example: '[Workook1.xls]Worksheet1';
 - In the **Item-Last Price** (last trade price) and **Item-Volume** (number of instruments in the last trade) fields, enter the addresses of the MS Excel cells from which data will be taken, in the 'RxCy' format, where 'x' is a row number, 'y' is a column number.
3. Click **Start**. If DDE2MS can find data to be processed, a table with the current OHLCV values will appear, the button name will change to **Stop** and the input fields will be disabled. Otherwise an error message will be displayed.

6.10.4 Using MetaServer RT

1. Launch MetaServerRT.
2. Check whether the source created in MetaStock ('SBER' in this example) is present in the list of available sources. If it isn't, select **Symbol-Add new** from the menu and enter the description of the created source (SBER).
3. Select the table row that corresponds to the new data source (contains its name in the 'TS / MS Symbol' column) and double click it to open the source configuration window.
4. In that window perform the following steps:
 - Enter the data source name in the **Global Server / MetaStock Symbol** field;
 - Enter 'Excel' in the **DDE** field.
5. Go to the Easy-Setup tools tab:
 - In the **Topic** field specify the Worksheet and Workbook containing QUIK data, in the format '[book_name.xls]sheet_name', for example: '[Workook1.xls]Worksheet1';
 - In the **Item** field specify the address of the cell that contains data, in the 'RxCy' format, where 'x' is a row number, 'y' is a column number: 'R1C1'.
6. Click the **Set** buttons.
7. Go back to the **Tradestation/MetaStock** tab and check all boxes. Click **OK**.
8. Click the green button (that has the **Start all instruments** tip) on the MetaServerRT program's toolbar. If the settings were configured correctly and the instrument data is available, the '*' parameter should change to '+' in the table row where the source is configured.

6.10.5 Configuration

Configuration of a data source for MetaStock is similar to that of the built-in export tools (see subsection [6.6 Configuring Equis MetaStock](#)).

To make MetaStock correctly handle fractional numbers, set '.' instead of ',' as the decimal separator in Windows' Regional Settings, otherwise data won't be transferred correctly.

6.11 Transaction Import

menu **Trading / Import transactions from file...**

6.11.1 Purpose

This feature is used to automatically send transactions prepared by an external program to the trading system and receive reports about transaction import.

6.11.2 Usage

QUIK exchanges data with external programs via text files that have specific format:

- *.tri is a file with transaction parameters;
- *.tro is a file that contains the results of sending transactions into a trading system;
- *.trr is a file that contains the log of transaction processing.

The pattern of interaction between the programs is as follows:

1. An external program creates a transaction with specified parameters and writes it as a new line into a .tri file. Transactions are identified by an additional unique integer parameter TRANS_ID.
2. The QUIK system reads the .tri file periodically at certain intervals and transfers unprocessed transactions to the trading system. If the description of a transaction does not match the accepted format, the transaction is rejected.
3. The result of these actions is written into a .tro file in the format that can be recognized by the external program. Each line in that file contains information about the processing of a transaction identified by its TRANS_ID parameter.
4. The external program reads the results of the operations (on MOEX) in the .tro file. The registration number of an order is specified in the text message (the 'DESCRIPTION' field) received from the trading system and in the ORDER_NUMBER parameter.

Before QUIK reads the .tri file for the first time, it reads the processed orders from the .tro file. The orders contained in the .tro file are considered processed, and the lines in the .tri file with the same TRANS_ID will be ignored. If the external program upon launch enumerates the orders from the beginning, remove the .tro file from the working directory before launching the program.



6.11.3 Format of .tri file

This file is a sequence of lines each of which contains information about a single transaction.

Transaction parameters are specified in the following format: 'PARAMETER_NAME=parameter_value' separated by ';'.

An Iceberg order transaction on MOEX should be specified in a special format, which can be found in the example below.

Parameters and their values:

Parameter	Description
CLASSCODE	The class code for the transaction, for example, TQBR. Required parameter.
SECCODE	The ID of the instrument in the transaction, for example, SBER.
ACTION	<p>The transaction type. Possible values include:</p> <ul style="list-style-type: none">– 'NEW_ORDER' refers to a new order;– 'NEW_NEG DEAL' refers to a new OTC order;– 'NEW_REPO_NEG DEAL' refers to a new REPO order;– 'NEW_EXT_REPO_NEG DEAL' refers to a new modified REPO (REPO-M) order;– 'NEW_STOP_ORDER' refers to a new stop order;– 'KILL_ORDER' cancels an order;– 'KILL_NEG DEAL' cancels an OTC or REPO order;– 'KILL_STOP_ORDER' cancels a stop order;– KILL_ALL_ORDERS withdraws all orders from the trading system;– «KILL_ALL_STOP_ORDERS» – cancels all stop orders;– KILL_ALL_NEG_DEALS - withdraws all orders for OTC and REPO trades;– 'KILL_ALL_FUTURES_ORDERS' cancels all orders on the FORTS market;– 'KILL_RTS_T4_LONG_LIMIT' removes an open positions limit on the RTS Standard spot market;– 'KILL_RTS_T4_SHORT_LIMIT' removes the limit of open positions of the client on the spot asset On the RTS Standard market;– 'MOVE_ORDERS' moves orders on the FORTS market;– 'NEW_QUOTE' refers to a new non-addressed order;– 'KILL_QUOTE' cancels a non-addressed order;– 'NEW_REPORT' refers to a new order-report for transaction confirmation in the NDM and REPO modes;



Parameter	Description
	<ul style="list-style-type: none"> _ 'SET_FUT_LIMIT' refers to a new restriction on a futures account
FIRM_ID	The trader's identifier (firm ID).
ACCOUNT	The trader's account number. The parameter is required if 'ACTION' = 'KILL_ALL_FUTURES_ORDERS'. This parameter is case sensitive (upper / lower case characters)
CLIENT_CODE	A 20-characters compound field, which can contain a client code and a text comment (instruction) with the same separator that is used to enter orders manually. This parameter is only used for group transactions. Optional parameter
TYPE	The type of order, an optional parameter. Possible values include: 'L' refers to limited (by default), 'M' refers to market
MARKET MAKER ORDER	Indicates that the order is a Market maker's order. Possible values are 'YES' or 'NO'. The default value (if the parameter is not specified) is 'NO'
OPERATION	The direction of an order, a required parameter. Possible values include: 'S' refers to selling, 'B' refers to buying
EXECUTION_CONDITION	The execution condition of an order, an optional parameter. Possible values include: <ul style="list-style-type: none"> _ 'PUT_IN_QUEUE' refers to moving an order to the queue (default); _ 'FILL_OR_KILL' refers to immediate execution or cancelling; _ 'KILL_BALANCE' refers to withdrawal of balance
QUANTITY	The number of lots in an order, a required parameter
REPOVALUE	The value of a REPO-M trade in roubles
START_DISCOUNT	The initial discount value in an REPO-M order
LOWER_DISCOUNT	The minimum discount value in an REPO-M order
UPPER_DISCOUNT	The maximum discount value in an REPO-M order
PRICE	The order price, per instrument unit. Required parameter. When placing a market order (TYPE=M) to the FORTS derivatives market, specify the worst possible price (minimum or maximum, depending on direction). The order will be filled at the market price anyway. For other markets, specify price=0
STOPPRICE	Stop price, per instrument unit. Used only when 'ACTION' = 'NEW_STOP_ORDER'.
STOP_ORDER_KIND	The type of a stop order. Possible values include: <ul style="list-style-type: none"> _ 'SIMPLE_STOP_ORDER' refers to a stop-limit order; _ 'CONDITION_PRICE_BY_OTHER_SEC' refers to a conditional order with a condition on another security;



Parameter	Description
	<ul style="list-style-type: none"> – ‘WITH_LINKED_LIMIT_ORDER’ refers to an order with a linked order; – ‘TAKE_PROFIT_STOP_ORDER’ refers to a take-profit order; – ‘TAKE_PROFIT_AND_STOP_LIMIT_ORDER’ refers to a take-profit and stop-limit order; – ‘ACTIVATED_BY_ORDER_SIMPLE_STOP_ORDER’ refers to an ‘If done’ stop-limit order; – ‘ACTIVATED_BY_ORDER_TAKE_PROFIT_STOP_ORDER’ refers to an ‘If done’ take-profit order; – ‘ACTIVATED_BY_ORDER_TAKE_PROFIT_AND_STOP_LIMIT_ORDER’ refers to an ‘if done’ take-profit and stop-limit order. <p>If this parameter is missing, the order is considered to be a stop-limit order</p>
STOPPRICE_CLASSCODE	The class of the instrument used in the condition. Used only for ‘STOP_ORDER_KIND’ = ‘CONDITION_PRICE_BY_OTHER_SEC’
STOPPRICE_SECCODE	The code of the instrument used in the condition. Used only for ‘STOP_ORDER_KIND’ = ‘CONDITION_PRICE_BY_OTHER_SEC’
STOPPRICE_CONDITION	The direction of the stop price condition. Used only for ‘STOP_ORDER_KIND’ = ‘CONDITION_PRICE_BY_OTHER_SEC’. Possible values include: ‘<=’ or ‘>=’
LINKED_ORDER_PRICE	The price of a linked limit order. Used only for ‘STOP_ORDER_KIND’ = ‘WITH_LINKED_LIMIT_ORDER’
EXPIRY_DATE	Expiration date of a stop order. Possible values include: <ul style="list-style-type: none"> – GTC: before cancellation; – TODAY: before the today’s trading session ends; – Date format: YYYYMMDD
STOPPRICE2	The ‘stop limit’ condition price for a take-profit and stop-limit order
MARKET_STOP_LIMIT	The flag to indicate whether the order should be filled at the market price when the ‘stop limit’ condition is met. Possible values are ‘YES’ or ‘NO’. Applies to take-profit and stop-limit orders
MARKET_TAKE_PROFIT	The flag to indicate whether the order should be filled at the market price when the ‘take-profit’ condition is met. Possible values are ‘YES’ or ‘NO’. Applies to take-profit stop-limit orders
IS_ACTIVE_IN_TIME	The flag that indicates that a take-profit and stop-limit order will be valid during a certain period of time. Possible values are ‘YES’ or ‘NO’
ACTIVE_FROM_TIME	Time when an order of the ‘Take-profit and stop-limit’ type becomes valid, in the format HHMMSS
ACTIVE_TO_TIME	Time until which an order of the ‘Take profit and stop limit’ type remains valid, in



Parameter	Description
	the format HHMMSS
PARTNER	The code of the partner involved in an OTC transaction. Used for 'ACTION' = 'NEW_NEG DEAL', 'ACTION' = 'NEW_REPO_NEG DEAL' or 'ACTION' = 'NEW_EXT_REPO_NEG DEAL'
ORDER_KEY	The number of an order to be cancelled. Used for 'ACTION' = 'KILL_ORDER' or 'ACTION' = 'KILL_NEG DEAL' or 'ACTION' = 'KILL_QUOTE'
STOP_ORDER_KEY	The number of a stop order to be cancelled. Used for 'ACTION' = 'KILL_STOP_ORDER'
TRANS_ID	The id of an order with values from 1 to 2,294,967,294
SETTLE_CODE	A settlement code for OTC orders
PRICE2	A price of the second leg of a REPO transaction
REPOTERM	REPO period. This parameter relates to REPO-M trades
REPORATE	REPO rate as a percentage
BLOCK_SECURITIES	The flag that indicates that securities should be blocked during a REPO operation ('YES', 'NO')
REFUNDRATE	Fixed rate of refunding in case the 2nd part of REPO is not executed, as a percentage
COMMENT	A text comment specified in an order. Used when a group of orders is cancelled
LARGE_TRADE	The flag that indicates a large trade (YES / NO). This parameter relates to an OTC trade
CURR_CODE	The code of the currency used for settlements in an OTC trade, for example, 'SUR' refers to Russian roubles, 'USD' refers to US dollars. This parameter relates to an OTC trade
FOR_ACCOUNT	The person on whose behalf and at whose expense a trade is registered (relates to an OTC trade). Possible values include: <ul style="list-style-type: none"> _ OWNOWN: on your own behalf and at your own expense; _ OWNCLI: on your own behalf and at a client's expense; _ OWNDUP: on your own behalf and using trust funds; _ CLICLI: on a client's behalf and at his expense
SETTLE_DATE	Execution date of an OTC trade
KILL_IF_LINKED_ORDER_PARTLY_FILLED	The flag that indicates that a stop order should be cancelled after its linked limit order is partially executed. Used only for 'STOP_ORDER_KIND' = 'WITH_LINKED_LIMIT_ORDER'. Possible values are 'YES' or 'NO'



Parameter	Description
OFFSET	The offset of the last trade price from the maximum (minimum). Used for 'STOP_ORDER_KIND' = 'TAKE_PROFIT_STOP_ORDER' or 'ACTIVATED_BY_ORDER_TAKE_PROFIT_STOP_ORDER'
OFFSET_UNITS	Offset measurement units. Possible values are: <ul style="list-style-type: none"> _ 'PERCENTS' refers to percentage (with steps of 1/100th of percent); _ 'PRICE_UNITS' indicates that offset is measured in terms of price (with steps equal to price increments for this instrument) Used for 'STOP_ORDER_KIND' = 'TAKE_PROFIT_STOP_ORDER' or 'ACTIVATED_BY_ORDER_TAKE_PROFIT_STOP_ORDER'
SPREAD	Protective spread size. Used for 'STOP_ORDER_KIND' = 'TAKE_PROFIT_STOP_ORDER' or 'ACTIVATED_BY_ORDER_TAKE_PROFIT_STOP_ORDER'
SPREAD_UNITS	Protective spread measurement units. Possible values include: <ul style="list-style-type: none"> _ 'PERCENTS' refers to percentage (with steps of 1/100th of percent); _ 'PRICE_UNITS' indicates that offset is measured in terms of price (with steps equal to price increments for this instrument) Used for 'STOP_ORDER_KIND' = 'TAKE_PROFIT_STOP_ORDER' or 'ACTIVATED_BY_ORDER_TAKE_PROFIT_STOP_ORDER'
BASE_ORDER_KEY	The registration number of the primary order. Used for 'STOP_ORDER_KIND' = 'ACTIVATED_BY_ORDER_SIMPLE_STOP_ORDER' or 'ACTIVATED_BY_ORDER_TAKE_PROFIT_STOP_ORDER'
USE_BASE_ORDER_BALANCE	This flag specifies that the volume of an 'if done' order should be equal to the number of securities executed in the primary order. Possible values are: 'YES' or 'NO'. Used for 'STOP_ORDER_KIND' = 'ACTIVATED_BY_ORDER_SIMPLE_STOP_ORDER' or 'ACTIVATED_BY_ORDER_TAKE_PROFIT_STOP_ORDER'
ACTIVATE_IF_BASE_ORDER_PARTLY_FILLED	This parameter specifies that the 'if done' order should be activated when its primary order is partially filled. Possible values are: 'YES' or 'NO'. Used for 'STOP_ORDER_KIND' = 'ACTIVATED_BY_ORDER_SIMPLE_STOP_ORDER' or 'ACTIVATED_BY_ORDER_TAKE_PROFIT_STOP_ORDER'
BASE_CONTRACT	Identifier of the base contract for futures and options. This parameter is required for cancelling orders on the FORTS market.
MODE	The mode of moving orders on the FORTS market. This parameter relates to the action 'ACTION' = 'MOVE_ORDERS'. Possible values are: <ul style="list-style-type: none"> _ 0: do not change orders' volume; _ 1: change orders' volumes to new values; _ 2: if new and old values do not match in at least one order, both orders are canceled



Parameter	Description
FIRST_ORDER_NUMBER	The first order's number
FIRST_ORDER_NEW_ QUANTITY	The first order's volume
FIRST_ORDER_NEW_ PRICE	The first order's price
SECOND_ORDER_ NUMBER	The second order's number
SECOND_ORDER_NEW_ QUANTITY	The second order's quantity
SECOND_ORDER_NEW_ PRICE	The second order's price
KILL_ACTIVE_ORDERS	This attribute specifies that active orders for this instrument should be cancelled. Used only for 'ACTION' = 'NEW_QUOTE'. Possible values are: 'YES' or 'NO'
NEG_TRADE_OPERATION	The operation's direction in the trade confirmed by a report
NEG_TRADE_NUMBER	The number of the trade to be executed, confirmed by a report
VOLUMEMN	The limit of open positions, for 'Limit type' = 'Funds' or 'Total'
VOLUMEPL	The limit of open positions, for 'Limit type' = 'Secured funds'
KFL	Liquidity ratio
KGO	Client's collateral coefficient
USE_KGO	<p>This parameter determines whether to load the KGO value when the limits are loaded from a file:</p> <ul style="list-style-type: none"> _ for USE_KGO=Y, the KGO value is loaded; _ for USE_KGO=N, the KGO value is not loaded <p>When you place a limit in the MOEX derivatives market with mandatory reduction (see Section 7: Broker Operations, sub-section 7.18.1), you need to specify USE_KGO=Y</p>
CHECK_LIMITS	This parameter specifies whether the order's price will be checked for being within the acceptable price range. This parameter is used for the FORTS derivatives market. This is an optional parameter for transactions that place new orders in the 'FORTS Options' and 'OTC: FORTS Options' classes. Possible values are: 'YES' performs verification, 'NO' does not perform verification
MATCHREF	A reference that links two REPO or NDM transactions. Counterparties can enter into the transaction only if they specified the same value of this parameter in their orders. This parameter is an arbitrary sequence of up to 10 characters (both



Parameter	Description
	numbers and letters are allowed). Optional parameter
CORRECTION	The limit correction mode for futures account. Possible values are: — ‘Y’: enabled, setting a limit changes the current value; — ‘N’: disabled (default), specifying a limit sets a new value

The commands for conditional cancellation of groups of orders (‘KILL_ALL_ORDERS’, ‘KILL_ALL_STOP_ORDERS’, ‘KILL_ALL_NEG DEALS’, ‘KILL_ALL_FUTURES_ORDERS’) are processed as follows:

1. The ‘CLASSCODE’, ‘TRANS_ID’, ‘ACTION’, ACCOUNT parameters are required.
2. Possible optional parameters for commands for conditional cancellation of groups of orders:
 - ‘KILL_ALL_ORDERS’: ‘SECCODE’, ‘ACCOUNT’, ‘OPERATION’, ‘CLIENT_CODE’, ‘COMMENT’;
 - ‘KILL_ALL_STOP_ORDERS’: ‘SECCODE’, ‘ACCOUNT’, ‘OPERATION’, ‘CLIENT_CODE’, ‘COMMENT’, ‘EXPIRY_DATE’;
 - ‘KILL_ALL_NEG DEALS’: ‘SECCODE’, ‘ACCOUNT’, ‘OPERATION’, ‘CLIENT_CODE’, ‘COMMENT’, ‘PARTNER’, ‘SETTLE_CODE’;
 - ‘KILL_ALL_FUTURES_ORDERS’: ‘SECCODE’, ‘ACCOUNT’, ‘OPERATION’, ‘COMMENT’, ‘CLIENT_CODE’, ‘BASE_CONTRACT’.
3. The orders that match all parameters (logical ‘AND’) specified in the transaction will be cancelled.

Moving orders on the FORTS market is performed as follows:

- If MODE=0, then the FIRST_ORDER_NUMBER and SECOND_ORDER_NUMBER orders are cancelled. Two new orders are sent into the trading system. Their prices will be changed while their volume will remain the same;
- If MODE=1, then the FIRST_ORDER_NUMBER and SECOND_ORDER_NUMBER orders are cancelled. Two new orders are sent into the trading system. Both the price and volume of the orders will be changed;
- If MODE=2, then the FIRST_ORDER_NUMBER and SECOND_ORDER_NUMBER orders are cancelled. If the number of securities in both of the cancelled orders equals the values specified after FIRST_ORDER_NEW_QUANTITY and SECOND_ORDER_NEW_QUANTITY, two new orders with the corresponding parameters are sent into the trading system.

Examples of lines that might be contained in this file:



Transaction	Line
A sell order Rostelecom, limit order, 3 lots for 43.21 roubles each.	ACCOUNT=NL0080000043; CLIENT_CODE=467; TYPE=L; TRANS_ID=1; CLASSCODE=TQBR; SECCODE=RU0008943394; ACTION=NEW_ORDER; OPERATION=S; PRICE=43,21; QUANTITY=3;
A buy order LUKOIL, limit order, 3 lots for 253.3 roubles each.	ACCOUNT=NL0080000043; CLIENT_CODE=467; TYPE=L; TRANS_ID=2; CLASSCODE=TQBR; SECCODE=LKOH; ACTION=NEW_ORDER; OPERATION=B; PRICE=253,3; QUANTITY=3;
A buy order Rushydro, market order, 15 lots.	ACCOUNT=NL0080000043; CLIENT_CODE=467; TYPE=M; TRANS_ID=7; CLASSCODE=TQBR; SECCODE=HYDR; ACTION=NEW_ORDER; OPERATION=B; PRICE=0; QUANTITY=15;
A sell order LKOH-3.10 futures, market, 15 contracts.	ACCOUNT=SPBFUT00009; CLIENT_CODE= SPBFUT00009; TYPE=M; TRANS_ID=8; CLASSCODE=SPBFUT; SECCODE=LKHO; ACTION=NEW_ORDER; OPERATION=S; PRICE=16231; QUANTITY=15;
An OTC buy order Rostelecom, limit order, 1 lot for 42.81 roubles.	ACCOUNT=NL0080000043; CLIENT_CODE=467; TYPE=L; TRANS_ID=3; CLASSCODE=PSEQ; SECCODE=RU0008943394; ACTION= NEW_NEG_DEAL; OPERATION=B; PRICE=42,81; QUANTITY=1; PARTNER=NC0080000000;
An OTC sell order RusHydro, limit order, 3 lots for 1.113 roubles each.	ACCOUNT=NL0080000043; CLIENT_CODE=467; TYPE=L; TRANS_ID=4; CLASSCODE=PSEQ; SECCODE=HYDR; ACTION=NEW_NEG_DEAL; OPERATION=S; PRICE=1,113; QUANTITY=3; PARTNER=NC0080100000;
An order for REPO trade Gasprom, selling 10 lots for 100 roubles each, within 4 days, with R90 settlements.	ACTION=NEW_REPO_NEG_DEAL; TRANS_ID=135; CLASSCODE=RPMA; SECCODE=GAZP; ACCOUNT=NL0080000043; CLIENT_CODE=E1//NOTE; PARTNER=NC0038900000; OPERATION=S; QUANTITY=10; PRICE=100; SETTLE_CODE=R90; REPOTERM=4; REPORATE=5; REFUNDRATE=6;
An order for REPO-M trade Lukoil, buying 10 lots for 16,000 roubles total, within 1 day, with S0 settlements. To execute the trade, the counterparty must place a counter-order specifying 'link' in the Reference field	ACTION=NEW_EXT_REPO_NEG_DEAL; TRANS_ID=19; CLASSCODE=RPMA; SECCODE=LKOH; ACCOUNT=NL0080000043; CLIENT_CODE=Q7//NOTE; PARTNER=NC0080100000; OPERATION=B; QUANTITY=10; REPOVALUE=16000; SETTLE_CODE=S0; REPOTERM=1; REPORATE=0; REFUNDRATE=0; BLOCK_SECURITIES=NO; MATCHREF=link
An order for REPO with CCP 1 day trade Buying 1000000.00 at 6.1500	TRANS_ID=1; CLASSCODE=EQRP_BND; ACTION=New order (CCP); Trade account=L01+00000F00; Order operation=Buy; Order type=Limit; Price splitting flag=At different prices; Fill or kill=Put in queue; Price enter as...=By price; Is market-maker=By default; Security board=EQRP_BND; Instrument=RU000AOJRF37; Price=6.1500; Quantity=0; Comment=4F161/T2/; Order value=1000000.00; External user id=; Add. info=;
An OTC trade RusHydro, selling 30 lots for 19.332 roubles each.	CLIENT_CODE=2/3; TRANS_ID=8; CLASSCODE=SCVC; SECCODE=HYDR; ACTION=NEW_NEG_DEAL; OPERATION=B; PRICE=19.332; QUANTITY=30; SETTLE_CODE=UPTO5; LARGE_TRADE=YES; Curr_CODE=RUB; FOR_ACCOUNT=OWNCLI; SETTLE_DATE=20070620;



Transaction	Line
A stop limit RusHydro, 100 lots for selling at 7.000, the stop price is 7.300, the expiration date is 05.19.2011.	ACTION=NEW_STOP_ORDER; ACCOUNT= NL0080000043; TRANS_ID=17; CLASSCODE=TQBR; SECCODE=HYDR; OPERATION=S; QUANTITY=100; CLIENT_CODE=467; STOPPRICE=7.3; PRICE=7.0; EXPIRY_DATE=20110519;
A stop order with a condition on another security, Rostelecom -ao, selling 15 lots at 7.000, the condition is based on Rostelecom -ap, the stop price condition is <= 8.000.	ACTION=NEW_STOP_ORDER; STOP_ORDER_KIND=CONDITION_PRICE_BY_OTHER_SEC; ACCOUNT= NL0080000043; QUANTITY=15; TRANS_ID=15; CLASSCODE=TQBR; SECCODE=RTKM; STOPPRICE_CLASSCODE=TQBR; STOPPRICE_SECCODE=RTKMP; STOPPRICE_CONDITION=<; OPERATION=S; CLIENT_CODE=1001; STOPPRICE=8.0; PRICE=7.0;
A stop order with a linked order RusHydro, buying 15 lots for 8.500 each, stop price >= 8.000, and limit order at 6.000.	ACTION=NEW_STOP_ORDER; STOP_ORDER_KIND=WITH_LINKED_LIMIT_ORDER; ACCOUNT= NL0080000043; TRANS_ID=16; CLASSCODE=TQBR; SECCODE=HYDR; OPERATION=B; QUANTITY=15; CLIENT_CODE=1001; STOPPRICE=8.0; PRICE=8.5; LINKED_ORDER_PRICE=6.0; KILL_IF_LINKED_ORDER_PARTLY_FILLED=NO;
Take-profit Lukoil, buying 1 lot, activation when the price reaches 265, with an offset of 5% and protective interval of 5 pips, the expiration date is 07/06/2010.	ACTION=NEW_STOP_ORDER; TRANS_ID=8; STOP_ORDER_KIND=TAKE_PROFIT_STOP_ORDER; STOPPRICE=265; CLIENT_CODE=Q5; OPERATION=B; SECCODE=LKOH; CLASSCODE=TQBR; ACCOUNT=L01-00000F00; QUANTITY=1; EXPIRY_DATE=20100706; OFFSET=5; OFFSET_UNITS=PERCENTS; SPREAD=5; SPREAD_UNITS=PRICE_UNITS;
Take-profit and stop-limit Lukoil, buying 1 lot, take-profit is activated when the price reaches 2000, with an offset of 5% and protective spread of 3%, stop price is 2222, limit order price is 2255, valid from 10:00:01 to 19:45:45.	ACTION=NEW_STOP_ORDER; TRANS_ID=10055; CLASSCODE= TQBR; SECCODE=LKOH; ACCOUNT=L01-00000F00; CLIENT_CODE=Q7; OPERATION=B; QUANTITY=1; PRICE=2255; STOPPRICE=2000; STOP_ORDER_KIND=TAKE_PROFIT_AND_STOP_LIMIT_ORDER; OFFSET=5; OFFSET_UNITS=PERCENTS; SPREAD=3; SPREAD_UNITS=PERCENTS; MARKET_TAKE_PROFIT=NO; STOPPRICE2=2222; IS_ACTIVE_IN_TIME=YES; ACTIVE_FROM_TIME=100001; ACTIVE_TO_TIME=194545; MARKET_STOP_LIMIT=NO
Take-profit when an order is executed when order 81874488 is partially filled, place a take-profit order for Lukoil in the amount of the filled part of the primary order; when the price reaches 265, with an offset of 10 pips and the protective interval of 10 pips.	ACTION=NEW_STOP_ORDER; TRANS_ID=11; STOP_ORDER_KIND=ACTIVATED_BY_ORDER_TAKE_PROFIT_STOP_ORDER; BASE_ORDER_KEY=81874488; USE_BASE_ORDER_BALANCE=yes; ACTIVATE_IF_BASE_ORDER_PARTLY_FILLED=yes; SPREAD=10; OFFSET=10; OFFSET_UNITS=PRICE_UNITS; SPREAD_UNITS=PRICE_UNITS; STOPPRICE=265; CLIENT_CODE=Q5; OPERATION=B; SECCODE=LKOH; CLASSCODE=TQBR; ACCOUNT=L01-00000F00;



Transaction	Line
Stop limit when an order is filled when order 81874488 is partially filled, place stop limit for Lukoil in the amount of the filled part of the primary order, with the stop price of 271 and the order price of 270.	ACTION=NEW_STOP_ORDER; TRANS_ID=12; STOP_ORDER_KIND=ACTIVATED_BY_ORDER_SIMPLE_STOP_ORDER; BASE_ORDER_KEY=81874488; USE_BASE_ORDER_BALANCE=yes; ACTIVATE_IF_BASE_ORDER_PARTLY_FILLED=yes; PRICE=270; STOPPRICE=271; CLASSCODE=TQBR; SECCODE=LKOH; ACCOUNT=L01-00000F00; OPERATION=B; CLIENT_CODE=Q5;
'If done' take-profit and stop limit order when order 123456 is partially filled, place a take-profit order for Lukoil at the market price, activated when the price reaches 2000, with the offset of 5 pips, and stop limit: the stop price is 1990, execution at the market price.	ACTION=NEW_STOP_ORDER; TRANS_ID=10060; CLASSCODE= TQBR; SECCODE=LKOH; ACCOUNT=L01-00000F00; CLIENT_CODE=Q7; OPERATION=B; PRICE=2010; STOPPRICE=2000; STOP_ORDER_KIND=ACTIVATED_BY_ORDER_TAKE_PROFIT_AND_STOP_LIMIT_ORDER; OFFSET=5; OFFSET_UNITS=PRICE_UNITS; SPREAD=3; SPREAD_UNITS=PRICE_UNITS; BASE_ORDER_KEY=123456; USE_BASE_ORDER_BALANCE=YES; ACTIVATE_IF_BASE_ORDER_PARTLY_FILLED=YES; MARKET_TAKE_PROFIT=YES; STOPPRICE2=1990; MARKET_STOP_LIMIT=YES
* An iceberg order In the MOEX stock market, buy 100 lots of Aeroflot at 70 each, the visible number of lots in the queue is 10, the client code is 467.	CLASSCODE=TQBR; TRANS_ID=2; ACTION=Place Iceberg order; Trading account=S01-00000F00; B/S=Buying;Type=Limit;Type by price=by different prices; Type by balance=place in queue; Price value entry type=By price; Instrument=AFLT; Price=70; Lots=100; Visible number=10; Note=467;
Cancelling an order the number is 503983	CLASSCODE=TQBR; SECCODE=RU0009024277; TRANS_ID=5; ACTION=KILL_ORDER; ORDER_KEY=503983;
Cancelling an OTC order the number is 503984	CLASSCODE=TQBR; TRANS_ID=6; ACTION=KILL_NEG_DEAL; ORDER_KEY=503984;
Cancelling an OTC transaction the number is 3	ACTION=KILL_NEG_DEAL; TRANS_ID=25; CLASSCODE=SCVC; SECCODE=HYDR; ORDER_KEY=3; OPERATION=S; FIRM_ID=NC0038900000;
Cancelling all orders for the client with code Q6	TRANS_ID=1; CLASSCODE=TQBR; ACTION=KILL_ALL_ORDERS; CLIENT_CODE=Q6;
Cancelling all stop orders with a buy direction	TRANS_ID=2; CLASSCODE=TQBR; ACTION=KILL_ALL_STOP_ORDERS; OPERATION=B;
Cancelling all negotiated orders for the class 'OTC: grade 1 shares'	TRANS_ID=3; CLASSCODE=PSEQ; ACTION=KILL_ALL_NEG DEALS;



Transaction	Line
Cancelling all orders on the FORTS derivatives market placed to buy contracts on the assets of Rostelecom - ao	TRANS_ID=50; ACCOUNT=SPBFUT00001; ACTION=KILL_ALL_FUTURES_ORDERS; OPERATION=B; CLASSCODE=SPBFUT; BASE_CONTRACT=RTKM;
Removing an open positions limit in the RTS Standard spot market,	TRANS_ID=99; ACTION=KILL_RTS_T4_LONG_LIMIT; FIRM_ID= SPBFUT389; ACCOUNT=389_011; CLASSCODE=RTSST;
Removing a client's open positions limit on a spot asset in the RTS Standard market	TRANS_ID=117; ACTION=KILL_RTS_T4_SHORT_LIMIT; FIRM_ID= SPBFUT389; ACCOUNT=389_011; SECCODE=GAZP; CLASSCODE=RTSST;
Moving orders on the FORTS derivatives market	ACTION=MOVE_ORDERS; TRANS_ID=333; CLASSCODE=SPBFUT; SECCODE=EBM6; FIRM_ID=SPBFUT389; MODE=1; FIRST_ORDER_NUMBER=21445064; FIRST_ORDER_NEW_PRICE=10004; FIRST_ORDER_NEW_QUANTITY=4; SECOND_ORDER_NUMBER=21445065; SECOND_ORDER_NEW_PRICE=10004; SECOND_ORDER_NEW_QUANTITY=4;
A non-addressed order for buying RusHydrp, 1 lot at 15.0 roubles, T0 settlement code, with the 'NO' attribute of cancelling active nonspecific orders.	ACTION=NEW_QUOTE; TRANS_ID=779; CLASSCODE=PSEQ; SECCODE=HYDR; OPERATION=B; QUANTITY=1; PRICE=15.0; SETTLE_CODE=T0; KILL_ACTIVE_ORDERS=NO;
Cancelling a non-addressed order numbered 15919	ACTION=KILL_QUOTE; TRANS_ID=781; CLASSCODE=PSEQ; SECCODE=HYDR; ORDER_KEY=15919;
Import of limits on futures accounts for the account of Trader 389_011, where the 'Total' limit of open positions is 20 millions of roubles, and the limit of open positions 'Secured funds' is limited to 10 million roubles.	ACTION=SET_FUT_LIMIT; TRANS_ID=22; CLASSCODE=SPBFUT; ACCOUNT=389_011; VOLUMEMN=20000000,00; VOLUMEPL=10000000,00; KFL=0,00; KGO=0,00; USE_KGO=Y; FIRM_ID=SPBFUT389; CORRECTION=N
Confirmations of trades to be executed by a report with number 179205900	ACTION=NEW_REPORT; TRANS_ID=15; CLASSCODE=RPMA; NEG_TRADE_OPERATION=B; NEG_TRADE_NUMBER=179205900;

* – an order is sent using the common method



6.11.4 The format of .tro file with transaction processing results

This file is a sequence of lines each of which contains information about a single transaction. Transaction parameters are specified as 'PARAMETER_NAME=parameter_value' separated by ':'.

Parameters and their values:


Parameter	Description
TRANS_ID	Unique identification number of an order
STATUS	The result of the operation. It can have one of the following values: <ul style="list-style-type: none">_ '0': the transaction was sent to server;_ '1': the transaction was received by the QUIK server from the client;_ '2': error during sending the transaction to the trading system due to loss of connection to MOEX gateway; the transaction cannot be sent again;_ '3': the transaction is made;_ '4': the transaction is not made in the trading system; the trading system error code will be specified in the 'DESCRIPTION' field;_ '5': the transaction was not verified by the QUIK server. For example, the user has no rights to send transactions of this type;_ '6': the transaction didn't pass the check for limits by the QUIK server;_ '10': the transaction is not supported by the trading system. For example, it was an attempt to send 'ACTION = MOVE_ORDERS' to MOEX;_ '11': the transaction didn't pass digital signature verification. For example, the server keys do not match the signature of the transaction sent to the server;_ '12': timeout for a transaction response has expired. This can happen when a transaction is sent using QPILE;_ '13': the transaction is rejected as its execution could have resulted in a cross-trade (i.e, a trade with the same client account)
TRANS_NAME	A description of the transaction, for example, 'Order entry'
DESCRIPTION	A text comment to the STATUS field containing the response from the QUIK server or trading system
ORDER_NUMBER	Registration number of an order in the trading system

An example of a line in the .tro file:

```
TRANS_ID=14;STATUS=0;TRANS_NAME="Order entry"; DESCRIPTION="Transaction sent";
TRANS_ID=14;STATUS=3;TRANS_NAME="Order entry"; DESCRIPTION="(160) Buy order N
68359610 is registered."; ORDER_NUMBER=68359610;
```



6.11.5 Configuration



1. Open the transaction import configuration window under **Trading / Import transactions from file....**
2. Enter the full path to a .tri file with transactions into the **Transactions file** field, for example, C:\quikdata\input.tri.
3. In the **Process each .. seconds** field, specify the frequency with which the file will be read. The recommended interval is 5 seconds.
4. If **Play sound when file is read** is selected, the program will beep every time the file is accessed. Use this option to monitor transactions import process.
5. Enter the full path to a .tro file into the **Successfully sent transactions file** field, for example, C:\quikdata\output.tro.
6. Enter the full path to a .trr file into the **Sent transactions log file** field, for example, C:\quikdata\log.trr.
7. If **Log sent transactions** is checked, the information about processed transactions will be written into that file.
8. The following elements (**Number of times the file was accessed**, etc) show the statistics for the import process.
9. Click **Start processing** to launch the transaction import process. Click **Stop processing** to stop this process.
10. Click **Close** to save the changes and close the configuration window. If the import process is launched, it will be performed automatically in the background.

Transaction data must be written into a text file as a single line. If the parameters of one transaction are written to the file in several steps, it could happen that QUIK will start reading the transaction before it has been completely written, in which case it will be rejected or processed incorrectly.

6.12 Importing transactions via API

menu **Trading / External transactions...**

6.12.1 Purpose

This function was designed to send transactions prepared by a client's program. This functionality is implemented in the **Trans2QUIK.dll** library. The functions from the library are described below. With the help of these functions, you can:

1. Establish or terminate a connection between a QUIK Workstation and **Trans2QUIK.dll**.
2. Check the connection between a QUIK Workstation and **Trans2QUIK.dll** and between a QUIK Workstation and the QUIK server.
3. Send a transaction.
4. Obtain information on orders and transactions.

There are two methods of transferring transactions: synchronous and asynchronous. They are implemented in different functions.

1. During synchronous transfer, the function finishes only after a response is received from the QUIK server. Therefore synchronous transactions can only be sent sequentially, waiting for a response to every sent transaction - this method is simpler and more suitable for programmers who have little experience in application development.
2. During asynchronous transfer, the function exits immediately. The answers about sent asynchronous transactions are received through a callback function. This function is called each time an answer about a performed or rejected transaction is received. Transaction execution statuses that are returned in the callback function are described along with the statuses used for sending transactions via a file (see sub-section [6.11](#)).

Another callback function is provided to control connections between a QUIK terminal and **Trans2QUIK.dll** and between a QUIK Workstation and the QUIK server.


The transaction format for import via API is similar to the format used to import transaction via a file (see sub-section [6.11](#)). The following transaction types are not supported by **Trans2quik.dll**:

- KILL_ALL_ORDERS withdraws all orders from the trading system;
- KILL_ALL_STOP_ORDERS withdraws all stop orders;
- KILL_ALL_NEG DEALS withdraws all orders for OTC and REPO trades.



To obtain information about orders and transactions, the user must create a list of instruments to be received, separately for orders and transactions. Then the process of obtaining information with a callback is launched. When no more information about orders and transactions is received, the lists of received instruments are cleared. For further details, see sub-section [6.12.23](#).

6.12.2 Settings



Transaction import via API is configured in the **External transactions processing** dialogue (menu **Trading / External transactions...**).

To start processing of external transactions, click **Start processing**.

If **Start external transactions processing automatically** is checked, the service for processing external transactions starts when the QUIK Workstation is run.

The statistics on sent and received transactions is displayed in the **Number of received external transactions** and **Number of transactions sent to server** fields.

6.12.3 Constants

The constants returned upon exist from functions and procedures are described below:

Constant	Description
TRANS2QUIK_SUCCESS	0
TRANS2QUIK_FAILED	1
TRANS2QUIK_QUIK_TERMINAL_NOT_FOUND	2
TRANS2QUIK_DLL_VERSION_NOT_SUPPORTED	3
TRANS2QUIK_ALREADY_CONNECTED_TO_QUIK	4
TRANS2QUIK_WRONG_SYNTAX	5
TRANS2QUIK_QUIK_NOT_CONNECTED	6
TRANS2QUIK_DLL_NOT_CONNECTED	7
TRANS2QUIK_QUIK_CONNECTED	8



Constant	Description
TRANS2QUIK_QUIK_DISCONNECTED	9
TRANS2QUIK_DLL_CONNECTED	10
TRANS2QUIK_DLL_DISCONNECTED	11
TRANS2QUIK_MEMORY_ALLOCATION_ERROR	12
TRANS2QUIK_WRONG_CONNECTION_HANDLE	13
TRANS2QUIK_WRONG_INPUT_PARAMS	14

6.12.4 Functions

The list of functions to process transactions via API:

Function	Purpose
TRANS2QUIK_CONNECT	Connects Trans2QUIK.dll to a QUIK Workstation
TRANS2QUIK_DISCONNECT	Disconnects Trans2QUIK.dll from a QUIK Workstation
TRANS2QUIK_IS_DLL_CONNECTED	Checks connection between Trans2QUIK.dll and a QUIK Workstation
TRANS2QUIK_IS_QUIK_CONNECTED	Checks connection between a QUIK terminal and the QUIK server
TRANS2QUIK_SEND_SYNC_TRANSACTION	Sends a synchronous transaction
TRANS2QUIK_SEND_ASYNC_TRANSACTION	Sends an asynchronous transaction
TRANS2QUIK_CONNECTION_STATUS_CALLBACK	The prototype of the callback function used to monitor connections between Trans2QUIK.dll and a QUIK terminal in use or the QUIK terminal in use and the server
TRANS2QUIK_SET_CONNECTION_STATUS_CALLBACK	The prototype of the callback function used to handle received connection information
TRANS2QUIK_TRANSACTIONS_REPLY_CALLBACK	The prototype of the callback function used to handle received information about a sent transaction
TRANS2QUIK_SET_TRANSACTIONS_REPLY_CALLBACK	This function defines the TRANS2QUIK_TRANSACTIONS_REPLY_CALLBACK callback function
TRANS2QUIK_ORDER_STATUS_CALLBACK	The prototype of the callback function used to handle received information about an order



Function	Purpose
TRANS2QUIK_TRADE_STATUS_CALLBACK	The prototype of the callback function used to handle received information about a trade
TRANS2QUIK_SUBSCRIBE_ORDERS	Creates an instrument list by classes to receive orders
TRANS2QUIK_SUBSCRIBE_TRADES	Creates an instrument list by classes to receive trades
TRANS2QUIK_START_ORDERS	Initiates the process of receiving orders for the instruments from the list created by the TRANS2QUIK_SUBSCRIBE_ORDERS function previously
TRANS2QUIK_START_TRADES	Initiates the process of receiving trades for the instruments from the list created by the TRANS2QUIK_SUBSCRIBE_TRADES function previously
TRANS2QUIK_UNSUBSCRIBE_ORDERS	Stops the TRANS2QUIK_START_ORDERS function and clears the list of received instruments that was generated by the TRANS2QUIK_SUBSCRIBE_ORDERS function
TRANS2QUIK_UNSUBSCRIBE_TRADES	Stops the TRANS2QUIK_START_TRADES function and clears the list of received instruments that was generated by the TRANS2QUIK_SUBSCRIBE_TRADES function

6.12.5 TRANS2QUIK_CONNECT function

This function is used to connect **Trans2QUIK.dll** to a QUIK Workstation.

```
long  TRANS2QUIK_CONNECT(LPCSTR lpcstrConnectionStringString,
long* pnExtendedErrorCode, LPSTR lpstrErrorMessage, DWORD dwErrorMessageSize)
```

Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none"> - TRANS2QUIK_SUCCESS means a successful connection; - TRANS2QUIK_QUIK_TERMINAL_NOT_FOUND means that either INFO.EXE is not found in the specified directory or its external connections service is not running. In this case, the pnExtendedErrorCode parameter will be set to 0; - TRANS2QUIK_DLL_VERSION_NOT_SUPPORTED means that the Trans2QUIK.dll version is not supported by the specified INFO.EXE. The pnExtendedErrorCode parameter will be set to 0; - TRANS2QUIK_DLL_ALREADY_CONNECTED_TO QUIK means that the connection is already established. The pnExtendedErrorCode parameter will be set to 0;



Parameter	Description
	<ul style="list-style-type: none"> - TRANS2QUIK_FAILED means an error during the attempt to establish connection. The pnExtendedErrorCode will contain an additional error code
lpcstrConnectionParamsS	Type: pointer to String. The full path to the directory with INFO.EXE with which connection is to be established
pnExtendedErrorCode	Type: pointer to Long. In case of an error, contains an extended error code
lpstrErrorMessage	Type: pointer to String. Can contain an error message in case of an error
dwErrorMessageSize	Type: Long. Contains the length of the string pointed to by lpstrErrorMessage

6.12.6 TRANS2QUIK_DISCONNECT function

This function is used to disconnect Trans2QUIK.dll from a QUIK Workstation.

```
long TRANS2QUIK_DISCONNECT(long* pnExtendedErrorCode,
LPSTR lpstrErrorMessage, DWORD dwErrorMessageSize)
```

Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none"> - TRANS2QUIK_SUCCESS means that Trans2QUIK.dll is successfully disconnected from the QUIK workstation; - TRANS2QUIK_FAILED means an error during the attempt to disconnect. The pnExtendedErrorCode will contain an additional error code; - TRANS2QUIK_DLL_NOT_CONNECTED means that no connection was established before the attempt to disconnect. In this case the pnExtendedErrorCode variable may contain an additional error code
pnExtendedErrorCode	Type: pointer to Long. In case of an error, contains an extended error code
lpstrErrorMessage	Type: pointer to String. Can contain an error message in case of an error
dwErrorMessageSize	Type: Long. Contains the length of the string pointed to by lpstrErrorMessage

6.12.7 TRANS2QUIK_IS QUIK_CONNECTED function

This function is used to check if connection between a QUIK terminal and the server is established.

```
long TRANS2QUIK_IS QUIK_CONNECTED (long* pnExtendedErrorCode,
LPSTR lpstrErrorMessage, DWORD dwErrorMessageSize)
```

Parameter	Description
Result	Type: Long. The function can return the following values:



Parameter	Description
	<ul style="list-style-type: none"> – TRANS2QUIK_QUIK_CONNECTED means that a connection is established; – TRANS2QUIK_QUIK_NOT_CONNECTED means that a connection is not established; – TRANS2QUIK_DLL_NOT_CONNECTED means that there is no connection between Trans2QUIK.dll and a QUIK terminal. In this case you cannot verify if the QUIK terminal is connected to server
pnExtendedErrorCode	Type: pointer to Long. In case of an error, contains an extended error code
lpstrErrorMessage	Type: pointer to String. Can contain an error message in case of an error
dwErrorMessageSize	Type: Long. Contains the length of the string pointed to by lpstrErrorMessage

6.12.8 TRANS2QUIK_IS_DLL_CONNECTED function

This function is used to check if connection between a QUIK terminal and Trans2QUIK.dll is established.

```
long TRANS2QUIK_IS_DLL_CONNECTED (long* pnExtendedErrorCode,
LPSTR lpstrErrorMessage, DWORD dwErrorMessageSize)
```

Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none"> – TRANS2QUIK_DLL_CONNECTED means that the connection between Trans2QUIK.dll and a QUIK terminal was established; – TRANS2QUIK_DLL_NOT_CONNECTED means that there is no connection between Trans2QUIK.dll and a QUIK terminal
pnExtendedErrorCode	Type: pointer to Long. In case of an error, contains an extended error code
lpstrErrorMessage	Type: pointer to String. Can contain an error message in case of an error
dwErrorMessageSize	Type: Long. Contains the length of the string pointed to by lpstrErrorMessage

6.12.9 TRANS2QUIK_SEND_SYNC_TRANSACTION function

Synchronous sending of transaction. During synchronous sending, the function returns a value after the results of transaction execution are received or after the QUIK terminal is disconnected from the server.

```
long TRANS2QUIK_SEND_SYNC_TRANSACTION (LPSTR lpstTransactionString,
long* pnReplyCode, PDWORD pdwTransId, double* pdOrderNum,
LPSTR lpstrResultMessage, DWORD dwResultMessageSize, long* pnExtendedErrorCode,
LPSTR lpstErrorMessage, DWORD dwErrorMessageSize)
```



Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none"> – TRANS2QUIK_SUCCESS means that the transaction is successfully sent to the server; – TRANS2QUIK_WRONG_SYNTAX means that the transaction string is incorrect; – TRANS2QUIK_DLL_NOT_CONNECTED means that there is no connection between Trans2QUIK.dll and the QUIK terminal; – TRANS2QUIK_QUIK_NOT_CONNECTED means that there is no connection between the QUIK terminal and the server; – TRANS2QUIK_FAILED means that the function failed. The pnExtendedErrorCode variable can contain an additional error code
lpstrTransactionString	Type: pointer to String. A string that represents a transaction. The sting has the same format that is used to send transactions via a file
pnReplyCode	Type: pointer to Long. Contains a transaction execution status. The statuses are the same as those used for sending orders via a file (see sub-section 9)
pdwTransId	Type: pointer to Long. Contains TransID of the transaction specified by the user
pdOrderNum	Type: pointer to Double. In case of success, contains an order number in the trading system
lpstrResultMessage	Type: pointer to String. In case of success, contains a message from the trading system
dwResultMessageSize	Type: Long. Contains the length of the string pointed to by lpstrResultMessage
pnExtendedErrorCode	Type: pointer to Long. In case of an error, contains an extended error code
lpstrErrorMessage	Type: pointer to String. Can contain an error message in case of an error
dwErrorMessageSize	Type: Long. Contains the length of the string pointed to by lpstrErrorMessage.

6.12.10 TRANS2QUIK_SEND_ASYNC_TRANSACTION function

An asynchronous transaction transfer. During asynchronous transaction sending, the function exits immediately, while the result of the transaction processing is returned via an appropriate callback function.

```
long  TRANS2QUIK_SEND_ASYNC_TRANSACTION (LPSTR lpstTransactionString,
long* pnExtendedErrorCode, LPSTR lpstErrorMessage, DWORD dwErrorMessageSize);
```

Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none"> – TRANS2QUIK_SUCCESS means that the transaction is successfully sent to the server;



Parameter	Description
	<ul style="list-style-type: none"> – TRANS2QUIK_WRONG_SYNTAX means that the transaction string is incorrect; – TRANS2QUIK_DLL_NOT_CONNECTED means that there is no connection between Trans2QUIK.dll and the QUIK terminal; – TRANS2QUIK QUIK NOT CONNECTED means that there is no connection between the QUIK terminal and the server; – TRANS2QUIK FAILED means that an attempt to send a transaction failed. In this case the pnExtendedErrorCode variable may contain an additional error code
lpstrTransactionString	Type: pointer to String. A string that represents a transaction. The sting has the same format that is used to send transactions via a file
pnExtendedErrorCode	Type: pointer to Long. In case of an error, contains an extended error code
lpstrErrorMessage	Type: pointer to String. Can contain an error message in case of an error
dwErrorMessageSize	Type: Long. Contains the length of the string pointed to by lpstrErrorMessage

6.12.11 TRANS2QUIK_CONNECTION_STATUS_CALLBACK, the prototype of the callback function used to monitor connection state

The prototype of the callback function used to monitor connections between Trans2QUIK.dll and a QUIK terminal in use or the QUIK terminal in use and the server.

```
void TRANS2QUIK_CONNECTION_STATUS_CALLBACK (long nConnectionEvent,
long nExtendedErrorCode, LPSTR lpstrInfoMessage)
```

Parameter	Description
nConnectionEvent	Type: Long. The function can return the following values: <ul style="list-style-type: none"> – TRANS2QUIK QUIK CONNECTED means that the connection between a QUIK terminal and the server is established; – TRANS2QUIK QUIK DISCONNECTED means that the connection between a QUIK terminal and the server is closed; – TRANS2QUIK DLL CONNECTED means that the connection between the DLL and a QUIK terminal is established; – TRANS2QUIK DLL DISCONNECTED means that the connection between the DLL and a QUIK terminal is closed
pnExtendedErrorCode	Type: Long. In case of an error, contains an extended error code
lpstrErrorMessage	Type: pointer to String. Can contain an error message in case of an error



6.12.12 TRANS2QUIK_SET_CONNECTION_STATUS_CALLBACK function

The prototype of the callback function used to handle received connection information.

```
long TRANS2QUIK_SET_CONNECTION_STATUS_CALLBACK  
(TRANS2QUIK_CONNECTION_STATUS_CALLBACK pfConnectionStatusCallback,  
long* pnExtendedErrorCode, LPSTR lpstrErrorMessage, DWORD dwErrorMessageSize)
```

Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none">– TRANS2QUIK_SUCCESS means that the callback function is defined;– TRANS2QUIK_FAILED means that the callback function was not set. In this case the pnExtendedErrorCode variable might contain an additional error code
TRANS2QUIK_CONNECTION_STATUS_CALLBACK	Type: function pointer. It contains the address of the function that will process the information about the connection between Trans2QUIK.dll and a QUIK terminal or a QUIK terminal and the server
pnExtendedErrorCode	Type: pointer to Long. In case of an error, contains an extended error code
lpstrErrorMessage	Type: pointer to String. Can contain an error message in case of an error
dwErrorMessageSize	Type: Long. Contains the length of the string pointed to by lpstrErrorMessage

6.12.13 TRANS2QUIK_TRANSACTIONS_REPLY_CALLBACK, the prototype of the callback function used to handle received transaction information

The prototype of the callback function used to handle received information about a sent transaction.

IMPORTANT! You cannot send transactions asynchronously with a callback and synchronously at the same time. This is because the callback function cannot be correctly called at the moment when the function for synchronous processing of transactions has not finished.

```
void TRANS2QUIK_TRANSACTION_REPLY_CALLBACK(long nTransactionResult,  
long nTransactionExtendedErrorCode, long nTransactionReplyCode, DWORD dwTransId,  
double dOrderNum, LPSTR lpstrTransactionReplyMessage)
```

Parameter	Description
nTransactionResult	Type: Long. The function can return the following values: <ul style="list-style-type: none">– TRANS2QUIK_SUCCESS means a transaction was sent successfully;– TRANS2QUIK_DLL_NOT_CONNECTED means that there is no connection between Trans2QUIK.dll and the QUIK terminal;



Parameter	Description
	<ul style="list-style-type: none"> – TRANS2QUIK_NOT_CONNECTED means that there is no connection between the QUIK terminal and the server; – TRANS2QUIK_FAILED means that an attempt to send a transaction failed. In this case the pnExtendedErrorCode variable may contain an additional error code
nTransactionExtendedError Code	Type: Long. If the callback function fails, this variable may contain an extended error code
nTransactionReplyCode	Type: Long. The pointer that contains transaction execution status. The statuses are the same as those used for sending orders via a file
dwTransId	Type: Long. The value of TransId of the registered transaction
dOrderNum	Type: Double. The order number assigned by the trading system when the transaction is executed
lpstrTransactionReplyMessage	Type: pointer to String. A message from the trading system or QUIK server

6.12.14 TRANS2QUIK_SET_TRANSACTIONS_REPLY_CALLBACK function

Sets the callback function for receiving information about the transactions sent asynchronously.

```
long TRANS2QUIK_SET_TRANSACTIONS_REPLY_CALLBACK
(TRANS2QUIK_TRANSACTION_REPLY_CALLBACK pfTransactionReplyCallback,
 long* pnExtendedErrorCode, LPSTR lpstrErrorMessage, DWORD dwErrorMessageSize)
```

Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none"> – TRANS2QUIK_SUCCESS means that the callback function is defined; – TRANS2QUIK_FAILED means that the callback function was not set. In this case the pnExtendedErrorCode variable might contain an additional error code
TRANS2QUIK_TRANSACTION_REPLY_CALLBACK	Type: function pointer. Points to the function that will process information about a sent transaction
pnExtendedErrorCode	Type: pointer to Long. In case of an error, contains an extended error code
lpstrErrorMessage	Type: pointer to String. Can contain an error message in case of an error
dwErrorMessageSize	Type: Long. Contains the length of the string pointed to by lpstrErrorMessage



6.12.15 TRANS2QUIK_ORDER_STATUS_CALLBACK function

The callback function for receiving information about order parameters.

```
void TRANS2QUIK_ORDER_STATUS_CALLBACK (long nMode, DWORD dwTransID,  
double dNumber, LPSTR lpstrClassCode, LPSTR lpstrSecCode, double dPrice,  
long nBalance, double dValue, long nIsSell, long nStatus, long nOrderDescriptor)
```

Parameter	Description
nMode	Type: Long. The attribute specifying whether initial reception of orders is being performed. The possible values include: '0' refers to a new order, '1' refers to initial reception of orders is in the process, '2' refers to receiving the final order from the initial sending.
dwTransID	Type: Long. The TransID of transaction that generated the order. Equals '0' if the order was not generated by a transaction from a file, or if TransID is unknown.
dNumber	Type: Double. Order number
lpstrClassCode	Type: pointer to String. Class code
lpstrSecCode	Type: pointer to String. Security code
dPrice	Type: Double. Order price.
nBalance	Type: Long. Unfilled amount of the order.
dValue	Type: Double. Order volume.
nIsSell	Type: Long. Order direction: '0' refers to 'Buying', other values mean 'Selling'.
nStatus	Type: Long. Order execution status: '1' refers to 'Active', '2' refers to 'Killed', otherwise 'Filled'.
nOrderDescriptor	Type: Long. An order descriptor, can be used for the following special functions in the callback function: <ul style="list-style-type: none">- long TRANS2QUIK_ORDER_QTY (long nOrderDescriptor) returns order quantity;- long TRANS2QUIK_ORDER_DATE (long nOrderDescriptor) returns order date;- long TRANS2QUIK_ORDER_TIME (long nOrderDescriptor) returns order time;- long TRANS2QUIK_ORDER_ACTIVATION_TIME (long nOrderDescriptor) returns order activation time;- long TRANS2QUIK_ORDER_WITHDRAW_TIME (long nOrderDescriptor) returns order cancellation time;- long TRANS2QUIK_ORDER_EXPIRY (long nOrderDescriptor) returns order expiration date;- double TRANS2QUIK_ORDER_ACCRUED_INT (long nOrderDescriptor) returns accrued coupon interest of the order;- double TRANS2QUIK_ORDER_YIELD (long nOrderDescriptor) returns order yield;



Parameter	Description
	<ul style="list-style-type: none"> – LPSTR TRANS2QUIK_ORDER_USERID (long nOrderDescriptor) returns the string identifier of the trader on whose behalf the order was placed; – long TRANS2QUIK_ORDER_UID (long nOrderDescriptor) returns the UserID specified in the order; – LPSTR TRANS2QUIK_ORDER_ACCOUNT (long nOrderDescriptor) returns the trading account specified in the order; – LPSTR TRANS2QUIK_ORDER_BROKERREF (long nOrderDescriptor) returns order comment; – LPSTR TRANS2QUIK_ORDER_CLIENT_CODE (long nOrderDescriptor) returns the code of the client who sent the order; – LPSTR TRANS2QUIK_ORDER_FIRMID (long nOrderDescriptor) returns the string identifier of the organization to which the user who sent the order belongs; – long TRANS2QUIK_ORDER_VISIBLE_QTY (long nOrderDescriptor) returns the visible quantity for Iceberg orders; – long TRANS2QUIK_ORDER_PERIOD (long nOrderDescriptor) returns the period in which the order was placed. The possible values include: '0' means 'Opening', '1' means 'Normal', '2' means 'Closing'. – FILETIME TRANS2QUIK_ORDER_FILETIME (long nOrderDescriptor) returns the date and time of order entry in the format YY.MM.DD HH:MM:SS.MS; – FILETIME TRANS2QUIK_ORDER_WITHDRAW_FILETIME (long nOrderDescriptor) returns the date and time of order cancellation in the format YY.MM.DD HH:MM:SS.MS; – long TRANS2QUIK_ORDER_DATE_TIME (long nOrderDescriptor, long nTimeType) returns the time parameters of the order depending on the value of nTimeType. The nTimeType can have the following values: <ul style="list-style-type: none"> – '0': the function returns the order's entry date in the format YYYYMMDD; – '1': the function returns the order's entry time in the format HHMMSS; – '2': the function returns microseconds of the order's entry time, an integer from 0 to 999999; – '3': the function returns the order's cancellation date in the format YYYYMMDD; – '4': the function returns the order's cancellation time in the format HHMMSS; – '5': the function returns microseconds of the order's cancellation time, an integer from 0 to 999999



6.12.16 TRANS2QUIK_TRADE_STATUS_CALLBACK function

The callback function for receiving information about a trade.

```
void TRANS2QUIK_TRADE_STATUS_CALLBACK (long nMode, double dNumber,  
double dOrderNum, LPSTR lpstrClassCode, LPSTR lpstrSecCode, double dPrice, long nQty,  
double dValue, long nIsSell, long nTradeDescriptor)
```

Parameter	Description
nMode	Type: Long. The attribute specifying whether initial reception of trades is being performed. The possible values include: '0' means a new trade, '1' means initial reception of trades is in the process, '2' means the final trade from initial sending is received
dNumber	Type: Double. Trade number
dOrderNum	Type: Double. Number of the order that generated the trade
lpstrClassCode	Type: pointer to String. Class code
lpstrSecCode	Type: pointer to String. Security code
dPrice	Type: Double. Trade price
nQty	Type: Long. Trade quantity
nIsSell	Type: Long. Trade direction: '0' refers to 'Buying', other values mean 'Selling'
dValue	Type: Double. Trade volume
nTradeDescriptor	Type: Long. A trade descriptor, can be used for the following special functions in the callback function: <ul style="list-style-type: none">- long TTRANS2QUIK_TRADE_DATE (long nTradeDescriptor) returns the trade date;- long TRANS2QUIK_TRADE_SETTLE_DATE (long nTradeDescriptor) returns the date of trade settlements;- long TRANS2QUIK_TRADE_TIME (long nTradeDescriptor) returns trade time;- long TRANS2QUIK_TRADE_IS_MARGINAL (long nTradeDescriptor) returns the flag that indicates if the trade is marginal: '0' refers to 'non-marginal', other values mean 'marginal'.- LPSTR TRANS2QUIK_TRADE_CURRENCY (long nTradeDescriptor) returns the currency of the instrument in the trade;- LPSTR TRANS2QUIK_TRADE_SETTLE_CURRENCY (long nTradeDescriptor) returns the settlement currency of the trade;- LPSTR TRANS2QUIK_TRADE_SETTLE_CODE (long nTradeDescriptor) returns the settlement code of the trade;- double TRANS2QUIK_TRADE_ACCRUED_INT (long nTradeDescriptor) returns the accrued coupon interest of the trade;



Parameter	Description
-	double TRANS2QUIK_TRADE_YIELD (long nTradeDescriptor) returns trade yield;
-	LPSTR TRANS2QUIK_TRADE_USERID (long nTradeDescriptor) returns the string identifier of the trader on which behalf the trade was executed;
-	LPSTR TRANS2QUIK_TRADE_ACCOUNT (long nTradeDescriptor) returns the trading account of the trade;
-	LPSTR TRANS2QUIK_TRADE_BROKERREF (long nTradeDescriptor) returns trade comment;
-	LPSTR TRANS2QUIK_TRADE_CLIENT_CODE (long nTradeDescriptor) returns the client code of the trade;
-	LPSTR TRANS2QUIK_TRADE_FIRMID (long nTradeDescriptor) returns the string identifier of the organization to which the user who executed the trade belongs;
-	LPSTR TRANS2QUIK_TRADE_PARTNER_FIRMID (long nTradeDescriptor) returns the string identifier of the trade partner's organization;
-	double TRANS2QUIK_TRADE_TS_COMMISION (long nTradeDescriptor) returns the total commission for this trade;
-	double TRANS2QUIK_TRADE_CLEARING_CENTER_COMMISION (long nTradeDescriptor) returns the clearing center's commission for this trade;
-	double TRANS2QUIK_TRADE_EXCHANGE_COMMISION (long nTradeDescriptor) returns the trade exchange commission for this trade;
-	double TRANS2QUIK_TRADE_TRADING_SYSTEM_COMMISION (long nTradeDescriptor) returns the commission for technical access for this trade;
-	double TRANS2QUIK_TRADE_PRICE2 (long nTradeDescriptor) returns the buyback price;
-	double TRANS2QUIK_TRADE_REPO_RATE (long nTradeDescriptor) returns the REPO rate as a percentage;
-	double TRANS2QUIK_TRADE_REPO_VALUE (long nTradeDescriptor) returns the REPO sum (the sum of funds attracted / provided for a REPO trade);
-	double TRANS2QUIK_TRADE_REPO2_VALUE (long nTradeDescriptor) returns the REPO buyback price;
-	double TRANS2QUIK_TRADE_ACCRUED_INT2 (long nTradeDescriptor) returns the accrued interest for buyback;
-	long TRANS2QUIK_TRADE_REPO_TERM (long nTradeDescriptor) returns the REPO period in calendar days;
-	double TRANS2QUIK_TRADE_START_DISCOUNT (long nTradeDescriptor) returns the initial discount as a percentage;
-	double TRANS2QUIK_TRADE_LOWER_DISCOUNT (long nTradeDescriptor) returns the lower limit of discount as a percentage;
-	double TRANS2QUIK_TRADE_UPPER_DISCOUNT (long nTradeDescriptor) returns the upper limit of discount as a percentage;
-	LPSTR TRANS2QUIK_TRADE_EXCHANGE_CODE (long nTradeDescriptor) returns



Parameter	Description
	<p>the exchange code as a string;</p> <ul style="list-style-type: none"> _ LPSTR TRANS2QUIK_TRADE_STATION_ID (long nTradeDescriptor) returns the string identifier of the workstation; _ long TRANS2QUIK_TRADE_BLOCK_SECURITIES (long nTradeDescriptor) returns the attribute indicating whether a financial instrument is blocked on a special account during a REPO operation: '0' refers to 'not blocked', other values mean 'blocked'; _ long TRANS2QUIK_TRADE_PERIOD (long nTradeDescriptor) returns the period in which the trade was performed. The possible values include: '0' refers to 'Opening', '1' refers to 'Normal', '2' refers to 'Closing'. _ FILETIME TRANS2QUIK_TRADE_FILETIME (long nTradeDescriptor) returns the date and time of a trade in the format YY.MM.DD HH:MM:SS.MS; _ long TRANS2QUIK_TRADE_DATE_TIME (long nTradeDescriptor, long nTimeType) returns the time parameters of a trade depending on the value of nTimeType. The nTimeType can have the following values: <ul style="list-style-type: none"> _ '0': the function returns the trade date in the format YYYYMMDD; _ '1': the function returns the trade time in the format HHMMSS; _ '2': the function returns microseconds of the trade time, an integer from 0 to 999999 _ long TRANS2QUIK_TRADE_KIND (long nTradeDescriptor) returns the trade's type. Possible values include: <ul style="list-style-type: none"> _ 1 - regular; _ 2 - negotiated; _ 3 - initial placement; _ 4 - cash / securities transfer; _ 5 - negotiated trade of the first REPO leg; _ 6 - swap transaction settlement trade; _ 7 - OTC swap transaction settlement trade; _ 8 - dual currency basket settlement trade; _ 9 - OTC dual currency basket settlement trade

6.12.17 TRANS2QUIK_SUBSCRIBE_ORDERS function

This function creates a list of classes of securities and instruments that is used to receive orders for these instruments.

long TRANS2QUIK_SUBSCRIBE_ORDERS (LPSTR lpstrClassCode, LPSTR lpstrSeccodes)



Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none"> – TRANS2QUIK_DLL_NOT_CONNECTED means that there is no connection between Trans2QUIK.dll and a QUIK terminal. In this case, you cannot subscribe to orders; – TRANS2QUIK QUIK_NOT_CONNECTED means that there is no connection between the QUIK Workstation and the server. In this case, you cannot subscribe to orders; – TRANS2QUIK_SUCCESS means a successful subscription,; – TRANS2QUIK FAILED means an attempt to subscribe failed
lpstrClassCode	Type: pointer to String. The code of the class to request orders. If both input parameters are empty strings, orders for all available instruments will be requested
lpstrSeccodes	Type: pointer to String. The list of security codes for which orders will be requested, separated by ' '. If an empty string is specified, orders will be requested for the class specified in the lpstrClassCode parameter.

6.12.18 TRANS2QUIK_SUBSCRIBE_TRADES function

This function creates a list of classes of securities and instruments that is used to receive trades for these instruments.

```
long TRANS2QUIK_SUBSCRIBE_TRADES (LPSTR lpstrClassCode, LPSTR lpstrSeccodes)
```

Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none"> – TRANS2QUIK_DLL_NOT_CONNECTED means that there is no connection between Trans2QUIK.dll and a QUIK terminal. In this case, you cannot subscribe to orders; – TRANS2QUIK QUIK_NOT_CONNECTED means that there is no connection between the QUIK Workstation and the server. In this case, you cannot subscribe to orders; – TRANS2QUIK_SUCCESS means a successful subscription,; – TRANS2QUIK FAILED means an attempt to subscribe failed
lpstrClassCode	Type: pointer to String. The code of the class to request trades. If both input parameters are empty strings, trades for all available instruments will be requested
lpstrSeccodes	Type: pointer to String. The list of security codes for which trades will be requested, separated by ' '. If an empty string is specified, trades will be requested for the class specified in the lpstrClassCode parameter

6.12.19 TRANS2QUIK_START_ORDERS function

This function launches the process of receiving orders for classes and instruments defined by the **TRANS2QUIK_SUBSCRIBE_ORDERS** function.



```
void TRANS2QUIK_START_ORDERS  
(TRANS2QUIK_ORDER_STATUS_CALLBACK pfnOrderStatusCallback)
```

Parameter	Description
TRANS2QUIK_ORDER_STATUS_CALLBACK	A pointer to a user callback function used to obtain information about orders

6.12.20 TRANS2QUIK_START_TRADES function

This function launches the process of receiving trades and parameters defined by the **TRANS2QUIK_SUBSCRIBE_TRADES** function.

```
void TRANS2QUIK_START_TRADES  
(TRANS2QUIK_TRADE_STATUS_CALLBACK pfnTradesStatusCallback)
```

Parameter	Description
TRANS2QUIK_TRADE_STATUS_CALLBACK	A pointer to a user callback function used to obtain information about trades

6.12.21 TRANS2QUIK_UNSUBSCRIBE_ORDERS function

This function stops the **TRANS2QUIK_START_ORDERS** function and clears the list of received instruments that was created by the **TRANS2QUIK_SUBSCRIBE_ORDERS** function.

```
long TRANS2QUIK_UNSUBSCRIBE_ORDERS ()
```

Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none">– TRANS2QUIK_DLL_NOT_CONNECTED means that there is no connection between Trans2QUIK.dll and a QUIK terminal. The operation cannot be performed;– TRANS2QUIK_QUIK_NOT_CONNECTED means that there is no connection between the QUIK Workstation and the server. The operation cannot be performed;– TRANS2QUIK_SUCCESS means the operation was performed successfully;– TRANS2QUIK_FAILED means an attempt to perform the operation failed

6.12.22 TRANS2QUIK_UNSUBSCRIBE_TRADES function

This function stops the **TRANS2QUIK_START_TRADES** function and clears the list of received instruments that was generated by the **TRANS2QUIK_SUBSCRIBE_TRADES** function.



```
long TRANS2QUIK_UNSUBSCRIBE_TRADES ()
```

Parameter	Description
Result	Type: Long. The function can return the following values: <ul style="list-style-type: none">– TRANS2QUIK_DLL_NOT_CONNECTED means that there is no connection between Trans2QUIK.dll and a QUIK terminal. The operation cannot be performed;– TRANS2QUIK_QUIK_NOT_CONNECTED means that there is no connection between the QUIK Workstation and the server. The operation cannot be performed;– TRANS2QUIK_SUCCESS means the operation was performed successfully;– TRANS2QUIK_FAILED means an attempt to perform the operation failed

6.12.23 Obtaining information about orders and trades

To obtain information about orders and transactions, the user must create a list of instruments to be received. To do this, call appropriate subscription functions: **TRANS2QUIK_SUBSCRIBE_ORDERS** for orders and **TRANS2QUIK_SUBSCRIBE_TRADES** for trades.

The list of instruments for both orders and trades can be generated using two methods: subscribing on the entire list for which the user has rights, or listing classes one by one. For example, if you need information for only two classes, TQNL and TQBR, and you are only interested in orders for the LKOH instrument in the class TQBR, the subscription should look as follows:

```
TRANS2QUIK_SUBSCRIBE_ORDERS ("TQNL", "");  
TRANS2QUIK_SUBSCRIBE_ORDERS ("TQBR", "LKOH");
```

To list several instruments in a class, use '|'. For example:

```
TRANS2QUIK_SUBSCRIBE_ORDERS ("TQBR", "LKOH|AFLT");
```

The 'l' separator cannot be used for listing classes of securities.

If the subscription function is called with a number of instruments that are already present in the list, such call will be ignored, for example:

```
TRANS2QUIK_SUBSCRIBE_ORDERS ("TQBR", "");  
TRANS2QUIK_SUBSCRIBE_ORDERS ("TQBR", "LKOH|AFLT");
```



First, a subscription to orders for all available classes and instruments was created, then, an attempt to subscribe to information for one particular class. This call will be ignored, as it does not add new instruments to the list of orders to be received. The following case will produce the same result:

```
TRANS2QUIK_SUBSCRIBE_ORDERS ("TQBR", "");  
TRANS2QUIK_SUBSCRIBE_ORDERS ("TQBR", "LKOH|AFLT");
```

To launch the process of receiving information on trades and orders, the user must call the **TRANS2QUIK_START_ORDERS** function for orders and **TRANS2QUIK_START_TRADES** for trades.

After calling these functions, your QUIK terminal will start transferring to **Trans2Quik.dll** the information about orders and trades with the specified callback functions. Information about already received trades and orders will be transferred first (the **nMode** parameter in the callback functions will be different from zero), and information about new orders and trades will be transferred as they arrive (the **nMode** parameter in callback functions will be zero).

To stop the process of receiving information on trades and orders, the user must call the corresponding unsubscribe functions: **TRANS2QUIK_UNSUBSCRIBE_ORDERS** for orders and **TRANS2QUIK_UNSUBSCRIBE_TRADES** for trades. These functions have no parameters and, when called, stop the process of receiving of information for all trades and orders. These functions as well as the functions for subscribing to trades and orders can be called multiple times. Example:

```
TRANS2QUIK_SUBSCRIBE_ORDERS ("", "");  
TRANS2QUIK_START_ORDERS ();  
TRANS2QUIK_SUBSCRIBE_TRADES ("", "");  
TRANS2QUIK_START_TRADES ();  
...  
TRANS2QUIK_UNSUBSCRIBE_ORDERS ();  
TRANS2QUIK_UNSUBSCRIBE_TRADES ();  
TRANS2QUIK_SUBSCRIBE_ORDERS ("TQBR", "LKOH");  
TRANS2QUIK_START_ORDERS ();  
TRANS2QUIK_SUBSCRIBE_TRADES ("TQBR", "LKOH");  
TRANS2QUIK_START_TRADES ();
```



6.13 APPENDICES

6.13.1 Data formats for configuring export via ODBC

Parameter	Format	Parameter	Format	Parameter	Format
Quotes Table					
Instrument	VARCHAR(200)	Close price	DECIMAL(15,6)	Strike	DECIMAL(15,6)
Security	VARCHAR(150)	Prev. VWAP	DECIMAL(15,6)	Price step	DECIMAL(15,6)
Security (s.n.)	VARCHAR(20)	Auction	VARCHAR(32)	Settle price	DECIMAL(15,6)
Security code	VARCHAR(12)	Accrued int.	DECIMAL(15,6)	Last trade qty	INTEGER
ISIN code	VARCHAR(15)	Yield	DECIMAL(15,6)	Change to prev. session	DECIMAL(15,6)
Reg. number	VARCHAR(20)	Coupon payment	DECIMAL(15,6)	prevsettleprice	DECIMAL(15,6)
Class	VARCHAR(128)	Yld. prev. VWAP	DECIMAL(15,6)	Price var. limit	DECIMAL(15,6)
Class code	VARCHAR(12)	Yld. VWAP	DECIMAL(15,6)	Price var. limit T+1	DECIMAL(15,6)
Trade date	VARCHAR(15)	Price-VWAP	DECIMAL(15,6)	Active order limit	DECIMAL(15,6)
Expiration	VARCHAR(15)	Close period	DECIMAL(15,6)	Neg. deal value.	DECIMAL(15,0)
Time to maturity	INTEGER	Close yield	DECIMAL(15,6)	Neg. deal qty	INTEGER
Face-value	DECIMAL(15,6)	% of last change	DECIMAL(15,6)	Current value	DECIMAL(15,6)
Currency	VARCHAR(4)	Pr. mark. price	DECIMAL(15,6)	Close value	DECIMAL(15,6)
Scale	INTEGER	Market price	DECIMAL(15,6)	Prev. close time	VARCHAR(15)
Price step	DECIMAL(15,6)	Market price 2	DECIMAL(15,6)	Open value	DECIMAL(15,6)
Status	VARCHAR(32)	Adm.quotation	DECIMAL(15,6)	Cur-Open index	DECIMAL(15,6)
Lot size	INTEGER	Next coup. pay	VARCHAR(15)	Cur-Close index	DECIMAL(15,6)
Session status	VARCHAR(32)	Coupon period	INTEGER	Last bid	DECIMAL(19,0)
Type	VARCHAR(12)	Price of offer	DECIMAL(15,6)	Last offer	DECIMAL(19,0)
Bid	DECIMAL(15,6)	Offer date	VARCHAR(15)	Prev.close price	DECIMAL(19,6)
Bid vol.	INTEGER	Issue size	INTEGER	Agg. rate	DECIMAL(15,6)
Total bid vol.	INTEGER	Prev. trd date	VARCHAR(15)	Type of price	VARCHAR(16)

Parameter	Format	Parameter	Format	Parameter	Format
Num. bids	INTEGER	Duration	DECIMAL(15,6)	Clear. status	VARCHAR(16)
Offer	DECIMAL(15,6)	Off. op. price	DECIMAL(15,6)	Clear. quote	DECIMAL(15,6)
Off. vol.	INTEGER	Off. cur. price	DECIMAL(15,6)	Auct. beg time	VARCHAR(15)
Tot. off. vol.	INTEGER	Off. close price	DECIMAL(15,6)	Auct. end time	VARCHAR(15)
Num. offers	INTEGER	Price type	VARCHAR(128)	Start ev.sess.	VARCHAR(15)
Open	DECIMAL(15,6)	Trend	DECIMAL(15,6)	End ev.sess.	VARCHAR(15)
High	DECIMAL(15,6)	Prev. adm. quote	DECIMAL(19,6)	Start morn. sess.	VARCHAR(15)
Low	DECIMAL(15,6)	Open pos.	INTEGER	End morn. sess.	VARCHAR(15)
Last	DECIMAL(15,6)	Highest price	DECIMAL(15,6)	curstepprice	VARCHAR(16)
Change	DECIMAL(15,6)	Lowest price	DECIMAL(15,6)	realvmpice	DECIMAL(15,6)
Quantity	INTEGER	Init. buy margin	DECIMAL(15,6)	Marg	VARCHAR(16)
Time	VARCHAR(15)	Init. sell margin	DECIMAL(15,6)	expdate	VARCHAR(15)
Vol.today	INTEGER	Change time	VARCHAR(15)	steppricecl	DECIMAL(15,6)
Val.today	DECIMAL(15,0)	Covered margin	DECIMAL(15,6)	steppriceprcl	DECIMAL(15,6)
Value	DECIMAL(15,6)	Not cov. margin	DECIMAL(15,6)	Min. cut. pr. time	VARCHAR(15)
VWAP	DECIMAL(15,6)	Opt. kind	VARCHAR(16)	Prev.lot size	INTEGER
High. bid	DECIMAL(15,6)	Base asset	VARCHAR(13)	D.lot.size ch.	VARCHAR(15)
Low. offer	DECIMAL(15,6)	Volatility	DECIMAL(15,6)	Offer date	VARCHAR(15)
Num. trades	INTEGER	Theor.price	DECIMAL(15,6)	Basic rate	DECIMAL(19,4)
Client portfolio table					
Firm	VARCHAR(12)	Current Leverage	DECIMAL(15,6)	LimBuy	DECIMAL(15,6)
Client code	VARCHAR(12)	Margin	DECIMAL(15,6)	LimSell	DECIMAL(15,6)
HighRisk	VARCHAR(12)	LimAll	DECIMAL(15,6)	LimNonMargin	DECIMAL(15,6)
Client type	VARCHAR(3)	AvLimAll	DECIMAL(15,6)	LimBuyAsset	DECIMAL(15,6)
Fut. trade account	VARCHAR(12)	LockedBuy	DECIMAL(15,6)	Pos. margin	DECIMAL(15,6)
InAssets	DECIMAL(15,6)	LockedBuyMargin	DECIMAL(15,6)	Orders margin	DECIMAL(15,6)
Leverage	DECIMAL(15,6)	LockedBuyAsset	DECIMAL(15,6)	Variat. margin	DECIMAL(15,6)



Parameter	Format	Parameter	Format	Parameter	Format
Open limit	DECIMAL(15,6)	LockedSell	DECIMAL(15,6)	Assets/Curr.clea r pos.	DECIMAL(15,6)
ValShort	DECIMAL(15,6)	LockedBuyNonMa rgin	DECIMAL(15,6)	Total money balance	DECIMAL(15,6)
ValLong	DECIMAL(15,6)	OpenAllAssets	DECIMAL(15,6)	Total locked money	DECIMAL(15,6)
ValLongMargin	DECIMAL(15,6)	AllAssets	DECIMAL(15,6)	Calc. params	VARCHAR(10)
ValLongAsset	DECIMAL(15,6)	ProfitLoss	DECIMAL(15,6)	Short (net)	DECIMAL(15,6)
Portfolio value	DECIMAL(15,6)	RateChange	DECIMAL(15,2)	Long (net)	DECIMAL(15,6)
Time and Sales Table					
Number	DECIMAL(15,0)	Security code	VARCHAR(12)	Yield	DECIMAL(15,6)
Trading date	VARCHAR(20)	Class	VARCHAR(130)	Accrued profit	DECIMAL(15,2)
Date	VARCHAR(20)	Class code	VARCHAR(12)	REPO rate (%)	DECIMAL(15,6)
Time	VARCHAR(15)	Price	DECIMAL(15,6)	REPO sum	DECIMAL(15,2)
Time(microsec)	INTEGER	Qty	INTEGER	REPO ransom value	DECIMAL(15,2)
Period	VARCHAR(20)	Volume	DECIMAL(15,2)	REPO period	INTEGER
Security (s.n.)	VARCHAR(20)	Operation	VARCHAR(12)		
Security	VARCHAR(150)	Settlement code	VARCHAR(5)		
Orders table					
Number	DECIMAL(15,0)	Depo account	VARCHAR(12)	Status	VARCHAR(10)
Exchange code	VARCHAR(64)	Price	DECIMAL(15,6)	Trans ID	INTEGER
Trading date	VARCHAR(20)	Qty	INTEGER	Settlement code	VARCHAR(12)
Date	VARCHAR(20)	Visible qty	DECIMAL(19,0)	Ransom price	DECIMAL(15,6)
Sent(time)	VARCHAR(10)	Balance	INTEGER	Market-maker's order	VARCHAR(3)
Sent(microsec)	INTEGER	Volume	DECIMAL(15,2)	BankAccID	VARCHAR(12)
Period	VARCHAR(20)	Currency	VARCHAR(4)	Value entry type	VARCHAR(16)

Parameter	Format	Parameter	Format	Parameter	Format
Activation time	VARCHAR(10)	Yield	DECIMAL(15,6)	REPO period	INTEGER
Killed date	VARCHAR(20)	Accrued interest	DECIMAL(15,2)	REPO sum	DECIMAL(15,2)
Killed(time)	VARCHAR(10)	Trader	VARCHAR(12)	REPO ransom value	DECIMAL(15,2)
Killed(microsec)	INTEGER	Dealer	VARCHAR(12)	REPO sum balance	DECIMAL(15,2)
Security (s.n.)	VARCHAR(20)	UID	INTEGER	Start discount (%)	DECIMAL(15,6)
Security	VARCHAR(150)	Client code	VARCHAR(20)	Reject reason	VARCHAR(128)
Security code	VARCHAR(12)	Comment	VARCHAR(20)	Execution type	VARCHAR(64)
Class	VARCHAR(130)	Linked order	DECIMAL(15,0)	Min qty	INTEGER
Class code	VARCHAR(12)	Expiration	VARCHAR(15)		
Side	VARCHAR(10)	Type	VARCHAR(10)		

Stop orders table

Number	DECIMAL(15,0)	Stop price direction	VARCHAR(3)	Active from	VARCHAR(12)
Date	VARCHAR(10)	Stop price	DECIMAL(15,6)	Active to	VARCHAR(12)
Time	VARCHAR(12)	Stop limit price direction	VARCHAR(3)	Type	VARCHAR(4)
Cancellation time	VARCHAR(10)	Stop-limit price	DECIMAL(15,6)	Status	VARCHAR(12)
Stop order type description	VARCHAR(128)	Price	DECIMAL(15,6)	Result	VARCHAR(64)
Description of the stop order type	VARCHAR(128)	Market stop limit	VARCHAR(2)	Linked order	DECIMAL(15,0)
Security (s.n.)	VARCHAR(16)	Qty	DECIMAL(15,0)	Linked order price	DECIMAL(15,6)
Security	VARCHAR(128)	Act. qty	DECIMAL(15,0)	Trans ID	DECIMAL(15,0)
Security code	VARCHAR(12)	Filled qty.	DECIMAL(15,0)	Offset from min / max	DECIMAL(15,6)



Parameter	Format	Parameter	Format	Parameter	Format
Class	VARCHAR(128)	Dealer	VARCHAR(12)	Offset units	VARCHAR(1)
Class code	VARCHAR(12)	UID	DECIMAL(15,0)	Protective spread	DECIMAL(15,6)
Operation	VARCHAR(8)	Client code	VARCHAR(128)	Spread units	VARCHAR(1)
Depo account	VARCHAR(12)	Comment	VARCHAR(20)	Take-profit at market price	VARCHAR(3)
Stop price sec.	VARCHAR(128)	Order number	DECIMAL(15,0)	Primary order	DECIMAL(15,0)
Stop-price sec. code	VARCHAR(12)	Condition trade	DECIMAL(15,0)	Server	VARCHAR(12)
Stop price sec. class	VARCHAR(128)	Expiration	VARCHAR(10)		
Stop price sec. class code	VARCHAR(12)	Active in time	VARCHAR(3)		
Trades table					
Number	DECIMAL(15,0)	Value	DECIMAL(15,2)	TS Commission	DECIMAL(15,6)
Exchange code	VARCHAR(68)	Currency	VARCHAR(4)	Clearing centre commission	DECIMAL(15,6)
Trading date	VARCHAR(20)	Settlement currency	VARCHAR(4)	Exchange commission	DECIMAL(15,6)
Settlement date	VARCHAR(10)	Settle code	VARCHAR(5)	TC commission	DECIMAL(15,6)
Time	VARCHAR(15)	Yield	DECIMAL(15,6)	Profit (%) for ransom date	DECIMAL(15,6)
Order number	DECIMAL(15,0)	Accrued profit	DECIMAL(15,2)	REPO sum	DECIMAL(15,2)
Security (s.n.)	VARCHAR(20)	Trader	VARCHAR(12)	REPO ransom value	DECIMAL(15,2)
Security	VARCHAR(150)	Station ID	VARCHAR(36)	REPO period	INTEGER
Security code	VARCHAR(12)	Dealer	VARCHAR(12)	Start discount (%)	DECIMAL(15,6)
Class	VARCHAR(130)	Trader's org.	VARCHAR(128)	Lower discount (%)	DECIMAL(15,6)
Class code	VARCHAR(12)	Client code	VARCHAR(20)	Upper discount (%)	DECIMAL(15,6)

Parameter	Format	Parameter	Format	Parameter	Format
Trade type	VARCHAR(12)	Broker reference	VARCHAR(20)	Block securities	VARCHAR(3)
Trade side	VARCHAR(10)	Partner	VARCHAR(12)	Trade date	VARCHAR(20)
Trade account	VARCHAR(12)	Partner's org.	VARCHAR(129)	Kind of trade	VARCHAR(64)
Price	DECIMAL(15,6)	Period	VARCHAR(20)	BankAccID	VARCHAR(12)
Time (μs)	INTEGER	Ransom price	DECIMAL(15,6)	Linked trade	DECIMAL(15,0)
Quantity	INTEGER	REPO rate (%)	DECIMAL(15,6)	Iceberg order	VARCHAR(4)

Table of cash limits

Firm	VARCHAR(12)	Incoming position	DECIMAL(15,6)	Total	DECIMAL(15,6)
Currency	VARCHAR(5)	Incoming limit	DECIMAL(15,6)	Available	DECIMAL(15,6)
Group	VARCHAR(5)	Current balance	DECIMAL(15,6)	Balance	DECIMAL(15,6)
Client code	VARCHAR(12)	Current limit	DECIMAL(15,6)		
Limit kind	VARCHAR(5)	Reserved	DECIMAL(15,6)		

Table of limits for securities

Firm	VARCHAR(12)	Incoming position	INTEGER	Available	INTEGER
Security	VARCHAR(150)	Incoming limit	INTEGER	Balance	INTEGER
Security code	VARCHAR(12)	Current balance	INTEGER	WA.position price	DECIMAL(15,6)
Depo account	VARCHAR(12)	Current limit	INTEGER		
Client code	VARCHAR(12)	Reserved	INTEGER		
Limit kind	VARCHAR(5)	Total	INTEGER		

Table of client account positions (futures)

Firm	VARCHAR(12)	Open short pos.	INTEGER	Act. on sell	INTEGER
Trade account	VARCHAR(12)	Open net pos.	INTEGER	Cur. pure pos. appr.	DECIMAL(15,6)
Security code	VARCHAR(12)	Cur. long pos.	INTEGER	Plan. pure pos.	DECIMAL(15,6)
Short name	VARCHAR(150)	Curr. short pos.	INTEGER	Variat. margin	DECIMAL(15,6)
Type	VARCHAR(35)	Curr. pure pos.	INTEGER	Effect. pos. price	DECIMAL(15,6)
Open long pos.	INTEGER	Act. on buy	INTEGER	Total v. margin	DECIMAL(15,2)



Parameter	Format	Parameter	Format	Parameter	Format
Expiration date	VARCHAR(20)	Position value	DECIMAL(19,4)	Real v. margin	DECIMAL(15,2)
Table of client account limits (futures)					
Firm	VARCHAR(12)	Open limit	DECIMAL(15,6)	Cur. clear positions (for orders)	DECIMAL(19,4)
Trade account	VARCHAR(12)	Cur. pure pos.	DECIMAL(15,6)	Cur. clear positions (for open positions)	DECIMAL(19,4)
Limit type	VARCHAR(20)	Plan. pure pos.	DECIMAL(15,6)	Coeff. of client marginal requirements	DECIMAL(19,6)
Liquid. coef.	DECIMAL(15,6)	Stock exchange tax	DECIMAL(19,4)	Holding currency	VARCHAR(4)
Options premium	DECIMAL(19,4)	Variation margin for positions	DECIMAL(15,6)	Real v. margin	DECIMAL(15,2)
Prev. open limit	DECIMAL(15,6)	Accrued profit	DECIMAL(15,6)		

Level II Quotes Table

Buy yield	DECIMAL(15,6)	Price	DECIMAL(15,6)	Sell total volume	INTEGER
Buy total volume	INTEGER			Sell yield	DECIMAL(15,6)
Own buy	INTEGER	Sell	INTEGER		
Buy	INTEGER	Own sell	INTEGER		

Table of order reports for NDM trades

Number	DECIMAL(15,0)	Trader	VARCHAR(12)	Qty	INTEGER
Date	VARCHAR(10)	Dealer	VARCHAR(12)	Value	DECIMAL(15,2)
Sent(time)	VARCHAR(8)	Trader's org.	VARCHAR(128)	Commission	DECIMAL(15,6)
Killed(time)	VARCHAR(8)	Depo account	VARCHAR(12)	Side	VARCHAR(32)
Class	VARCHAR(128)	Partner	VARCHAR(12)	Status	VARCHAR(32)
Security (s.n.)	VARCHAR(16)	Partner's org.	VARCHAR(128)	Report type	VARCHAR(32)



Parameter	Format	Parameter	Format	Parameter	Format
Security	VARCHAR(128)	Partner's depo account	VARCHAR(12)	Report kind	VARCHAR(32)
Table of trades for execution					
Number	DECIMAL(15,0)	Status	VARCHAR(32)	Upper discount (%)	DECIMAL(15,6)
Order number	DECIMAL(15,0)	Accrued profit	DECIMAL(15,2)	Block securities	VARCHAR(3)
Date	VARCHAR(10)	Price first REPO part	DECIMAL(15,6)	Execute	VARCHAR(3)
Settlement date	VARCHAR(10)	Ransom price	DECIMAL(15,6)	Execute tomorrow	VARCHAR(3)
Class	VARCHAR(128)	Trade number 1st REPO part	DECIMAL(15,0)	Type	VARCHAR(50)
Security ticker	VARCHAR(16)	REPO rate (%)	DECIMAL(15,6)	Direction	VARCHAR(12)
Security	VARCHAR(128)	Settle code	VARCHAR(12)	Discount after payment (%)	DECIMAL(15,6)
Side	VARCHAR(12)	Report	DECIMAL(15,0)	Quantity after payment	INTEGER
Client code	VARCHAR(128)	Partner's report	DECIMAL(15,0)	REPO sun after payment	DECIMAL(15,2)
Comment	VARCHAR(128)	TS Commission	DECIMAL(15,6)	REPO ransom sum after payment	DECIMAL(15,2)
Dealer	VARCHAR(12)	Balance	INTEGER	REPO return sum after payment	DECIMAL(15,2)
Trader's org.	VARCHAR(128)	Execution time	VARCHAR(10)	Date of settlement	VARCHAR(10)
Depo account	VARCHAR(12)	Engagement sum	DECIMAL(15,2)	Clearing status	VARCHAR(32)
Partner	VARCHAR(12)	REPO sum	DECIMAL(15,2)	Type of clearing	VARCHAR(32)
Partner's org.	VARCHAR(128)	REPO period	INTEGER	Report comission	DECIMAL(15,6)
Partner's depo account	VARCHAR(12)	REPO ransom value	DECIMAL(15,2)	Coupon payment	DECIMAL(15,6)

Parameter	Format	Parameter	Format	Parameter	Format
Price	DECIMAL(15,6)	REPO return value	DECIMAL(15,2)	Date of coupon payment	VARCHAR(10)
Qty	INTEGER	Discount (%)	DECIMAL(15,6)	Principal debt payment	DECIMAL(15,6)
Value	DECIMAL(15,2)	Lower discount (%)	DECIMAL(15,6)		
Date of principal debt payment	VARCHAR(10)	Settle currency	VARCHAR(5)		

Table liabilities and claims on assets

Firm	VARCHAR(12)	Class code	VARCHAR(12)	Sell qty	DECIMAL(15,0)
Security code	VARCHAR(12)	Class	VARCHAR(128)	Netto	DECIMAL(15,2)
Trading account	VARCHAR(12)	Depo account	VARCHAR(12)	Debit	DECIMAL(15,2)
Settle date	VARCHAR(10)	BankAccId	VARCHAR(12)	Credit	DECIMAL(15,2)
Security (s.n.)	VARCHAR(16)	Quantity	DECIMAL(15,0)		
Security	VARCHAR(128)	Buy qty	DECIMAL(15,0)		

Table of cash liabilities and claims

Firm	VARCHAR(12)	Settle date	VARCHAR(10)	Debit	DECIMAL(15,2)
BankAccId	VARCHAR(12)	Netto	DECIMAL(15,2)	Credit	DECIMAL(15,2)

Interest rate risk parameters table

Security code	VARCHAR(12)	Range start	DECIMAL(15,0)	REPO settlement rate, %	DECIMAL(15,2)
Security (s.n.)	VARCHAR(16)	Range end	DECIMAL(15,0)	High rate, %	DECIMAL(15,2)
Security	VARCHAR(128)	Discount, %	DECIMAL(15,1)	Range start, rur	DECIMAL(15,2)
Class code	VARCHAR(12)	Low rate, rur	DECIMAL(15,6)	Range end, rur	DECIMAL(15,2)
Class	VARCHAR(128)	REPO settlement rate, rur	DECIMAL(15,6)		
Settle date	VARCHAR(10)	High rate, rur	DECIMAL(15,6)		
Range	INTEGER	Low rate, %	DECIMAL(15,2)		



Parameter	Format	Parameter	Format	Parameter	Format
Market risk parameters table					
Security code	VARCHAR(12)	Range	INTEGER	High rate, rur	DECIMAL(15,6)
Security (s.n.)	VARCHAR(16)	Range start	DECIMAL(15,0)	Range end, rur	DECIMAL(15,2)
Security	VARCHAR(128)	Range end	DECIMAL(15,0)	Range end, rur	DECIMAL(15,2)
Class code	VARCHAR(12)	Discount, %	DECIMAL(15,1)		
Class	VARCHAR(128)	Low rate, rur	DECIMAL(15,6)		
Trading accounts table					
Firm	VARCHAR(12)	Depo account	VARCHAR(12)	Trading account type	VARCHAR(40)
Trading account	VARCHAR(12)	BankAccId	VARCHAR(12)	Depo account type	VARCHAR(30)
Main account	VARCHAR(12)	Description	VARCHAR(32)	Status	VARCHAR(20)

